



User's Guide

Acronis[®]
True Image Echo
Server for Windows

 **Acronis[®]**
COMPUTE WITH CONFIDENCE
WWW.ACRONIS.COM

Copyright © Acronis, Inc., 2000-2009. All rights reserved.

"Acronis" and "Acronis Secure Zone" are registered trademarks of Acronis, Inc.

"Acronis Compute with Confidence", "Acronis Startup Recovery Manager", "Acronis Active Restore" and the Acronis logo are trademarks of Acronis, Inc.

Linux is a registered trademark of Linus Torvalds.

Windows and MS-DOS are registered trademarks of Microsoft Corporation.

All other trademarks and copyrights referred to are the property of their respective owners.

Distribution of substantively modified versions of this document is prohibited without the explicit permission of the copyright holder.

Distribution of this work or derivative work in any standard (paper) book form for commercial purposes is prohibited unless prior permission is obtained from the copyright holder.

DOCUMENTATION IS PROVIDED «AS IS» AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Table of Contents

Chapter 1. Introduction	7
1.1 Acronis® True Image Echo Server – a complete solution for corporate users	7
1.2 New in Acronis True Image Echo Server	8
1.3 Supported file systems and storage media	9
1.3.1 Supported file systems	9
1.3.2 Supported storage media	10
1.4 Technical support	10
Chapter 2. Acronis True Image Echo Server installation and startup	12
2.1 System requirements	12
2.1.1 Minimum hardware requirements	12
2.1.2 Supported operating systems	12
2.2 Installing Acronis True Image Echo Server	12
2.2.1 Installation of Acronis True Image Echo Server	13
2.2.2 Acronis Universal Restore installation	13
2.3 Extracting Acronis True Image Echo Server components	14
2.4 Running Acronis True Image Echo Server	14
2.5 Removing Acronis True Image Echo Server	14
Chapter 3. General information and proprietary Acronis technologies	15
3.1 The difference between file archives and disk/partition images	15
3.2 Full, incremental and differential backups	15
3.3 Acronis Secure Zone®	16
3.4 Acronis Startup Recovery Manager	17
3.4.1 How it works	17
3.4.2 How to use	17
3.5 Acronis Active Restore	18
3.5.1 Limitations in using Acronis Active Restore	18
3.5.2 How it works	18
3.5.3 How to use	18
3.6 Acronis Universal Restore	19
3.6.1 Acronis Universal Restore purpose	19
3.6.2 Acronis Universal Restore general principles	20
3.6.3 Acronis Universal Restore and Microsoft Sysprep	20
3.6.4 Limitations in using Acronis Universal Restore	20
3.6.5 Getting Acronis Universal Restore	21
3.7 Backing up to tape drives	21
3.7.1 Restoring data from archives located on tape devices	22
3.8 Viewing disk and partition information	22
3.9 Changing Acronis temporary folder path	22
Chapter 4. Using Acronis True Image Echo Server	23
4.1 Main program window	23
4.2 Available operations	25
Chapter 5. Creating backup archives	28
5.1 Backing up files and folders (file backup)	28
5.2 Backing up disks and partitions (image backup)	32
5.3 Setting backup options	34
5.3.1 Archive protection	35
5.3.2 Source files exclusion	35
5.3.3 Pre/post commands	36

5.3.4 Database support.....	36
5.3.5 Compression level.....	37
5.3.6 Backup performance	37
5.3.7 Fast incremental/differential backup	38
5.3.8 Archive splitting.....	39
5.3.9 File-level security settings.....	39
5.3.10 Media components.....	40
5.3.11 Error handling.....	40
5.3.12 Dual destination backup.....	41
5.3.13 Additional settings.....	41
Chapter 6. Restoring the backup data	43
6.1 Considerations before recovery.....	43
6.1.1 Restore under Windows or boot from CD?.....	43
6.1.2 Network settings in rescue mode.....	43
6.1.3 Recovering dynamic volumes	44
6.2 Restoring files and folders from file archives	44
6.3 Restoring disks/partitions or files from images	47
6.3.1 Starting the Restore Data Wizard.....	48
6.3.2 Archive selection.....	48
6.3.3 Restoration type selection.....	48
6.3.4 Selecting a disk/partition to restore	50
6.3.5 Restoring NT disk signature	50
6.3.6 Selecting a target disk/partition.....	51
6.3.7 Changing the restored partition type.....	52
6.3.8 Changing the restored partition file system.....	52
6.3.9 Changing the restored partition size and location	53
6.3.10 Assigning a letter to the restored partition.....	53
6.3.11 Restoring several disks or partitions at once	53
6.3.12 Using Acronis Universal Restore.....	54
6.3.13 Setting restore options.....	55
6.3.14 Restoration summary and executing restoration.....	55
6.4 Setting restore options.....	55
6.4.1 Files to exclude from restoration.....	56
6.4.2 Files overwriting mode.....	56
6.4.3 Pre/post commands	56
6.4.4 Restoration priority.....	56
6.4.5 File-level security settings.....	56
6.4.6 Specifying mass storage drivers.....	57
6.4.7 Additional settings.....	57
6.4.8 Error handling.....	58
6.5 Creating dynamic disks and volumes	58
6.5.1 Creating dynamic volumes	59
Chapter 7. Scheduling tasks.....	61
7.1 Creating scheduled tasks.....	61
7.1.1 Setting up daily execution.....	63
7.1.2 Setting up weekly execution.....	64
7.1.3 Setting up monthly execution.....	65
7.1.4 Setting up one-time execution.....	65
7.1.5 Setting up event-driven execution	66
7.2 Managing scheduled tasks.....	66
Chapter 8. Managing the Acronis Secure Zone	68
8.1 Creating Acronis Secure Zone	68
8.2 Resizing the Acronis Secure Zone.....	70
8.3 Changing the password for Acronis Secure Zone	71
8.4 Managing backups in the Acronis Secure Zone	71

8.5 Deleting Acronis Secure Zone	72
Chapter 9. Creating bootable media	73
9.1 Creating Acronis rescue media	73
9.2 Creating a Win PE ISO with Acronis True Image Echo Server	75
Chapter 10. Operations with archives.....	76
10.1 Validating backup archives	76
10.2 Exploring archives and mounting images	76
10.2.1 Exploring an archive	77
10.2.2 Mounting an image.....	78
10.2.3 Unmounting an image	80
10.3 Consolidating backups.....	80
Chapter 11. Notifications and event tracing	84
11.1 Email notification	84
11.2 WinPopup notification	84
11.3 Viewing logs.....	85
11.4 Event tracing.....	86
11.4.1 Windows event log.....	86
11.4.2 SNMP notifications.....	87
11.5 Managing System Restore	87
Chapter 12. Working with a virtual environment	89
12.1 Backing up data on virtual machines	89
12.2 Recovering data on virtual machines	89
12.3 Using the disk conversion feature.....	90
12.3.1 Recover data on the VM.....	90
12.3.2 Recover both data and the VM	90
12.3.3 Physical to virtual migration	90
12.3.4 Converting workloads	91
12.4 Converting disk images to virtual disks	91
Chapter 13. Transferring the system to a new disk.....	93
13.1 General information	93
13.2 Security	93
13.3 Executing transfers	94
13.3.1 Selecting Clone mode	94
13.3.2 Selecting source disk	94
13.3.3 Selecting destination disk.....	95
13.3.4 Partitioned destination disk	96
13.3.5 Old and new disk partition layout.....	96
13.3.6 Old disk data	96
13.3.7 Destroying the old disk data.....	97
13.3.8 Selecting partition transfer method	98
13.3.9 Partitioning the old disk	99
13.3.10 Old and new disk partition layouts	99
13.3.11 Cloning summary.....	100
13.4 Cloning with manual partitioning	100
13.4.1 Old and new disk partition layouts	100
Chapter 14. Adding a new hard disk	102
14.1 Selecting a hard disk.....	102
14.2 Creating new partitions	102
14.3 Disk add summary	103
Chapter 15. Command-line mode and scripting	104
15.1 Working in the command-line mode	104

15.1.1	<i>TrueImageCmd.exe supported commands</i>	104
15.1.2	<i>Common options (options common for most trueimagecmd commands)</i>	107
15.1.3	<i>Specific options (options specific for individual trueimagecmd commands)</i>	108
15.1.4	<i>Trueimagecmd.exe usage examples</i>	113
15.1.5	<i>Ebasrvdb.exe tool: generate an XML file with the backup mapping details</i>	118
15.1.6	<i>Adv_report.exe: a report generation tool</i>	118
15.1.7	<i>Command-line mode usage under DOS</i>	118
15.2	<i>Scripting</i>	119
15.2.1	<i>Script execution parameters</i>	119
15.2.2	<i>Script structure</i>	119
15.2.3	<i>Script usage examples</i>	120

Chapter 1. Introduction

1.1 Acronis® True Image Echo Server – a complete solution for corporate users

Acronis True Image Echo Server is a comprehensive backup and recovery solution for a Windows-based server.

Acronis True Image Echo Server creates a transportable image, independent of the hardware platform that can be restored directly to and from any virtual or physical environment.

Minimizes downtime

Acronis True Image Echo Server enables you to restore systems in minutes, not hours or days. An entire system can be restored from an image that includes everything the system needs to run: the operating system, applications, databases, and configurations. It is not necessary to reinstall software or reconfigure your system or network settings. The complete system restoration can be performed to an existing system, to a new system with different hardware, or to virtual machines. With the Acronis Active Restore feature, users can access the server and begin working during the restore process, further decreasing downtime. File-level backups provide you with the flexibility to only backup specific, critical files.

Eases Administration

Wizards guide users through backup and recovery tasks, ensuring the product can be implemented with minimal user training.

Automates Backup

With the scheduling capability in Acronis True Image Echo Server, you simply create backup tasks, tailored by group, or certain times or events.

To ensure that backups have occurred, or if user intervention is required, you can request notifications via email or Windows Pop-up. You can view Acronis events in the Windows Application Events Log or Acronis own log files. Log messages can be automatically sent out to SNMP clients.

The product also supports the creation of custom commands before and after backups. For example, users can automatically run anti-virus products before an image is created and verify the validity of backups after the image has been created. And because these tasks can be scheduled, you need not recreate the script to run the pre- and post-event tasks each time; you can set the scheduled events once and they will run each time automatically.

Ensures 24 X 7 Uptime

With Acronis' patented drive snapshot technology, systems can be imaged while they are in use, ensuring 24-by-7 system availability. This technology enables the product to backup and image critical operating system files, the master boot record and any partition-based boot records without requiring a reboot. A CPU allocation feature allows you to limit the amount of CPU usage for the application to maximize the CPU's availability for mission critical applications. Additionally, users can control hard disk drive writing speeds and control network bandwidth used during backups, allowing minimal disruption of business operations.

A feature that allows you to suspend database activity for several seconds is provided so that you can create a valid image of mission-critical applications such as Microsoft Exchange Server, Microsoft SQL Server and Oracle. This database suspension process supports Microsoft's Volume Shadow Copy Service (VSS). If your database or operating system does not support VSS, Acronis True Image Echo Server will execute your custom commands to execute database suspension.

Leverages Existing Technology Investments

The product can leverage your current storage infrastructure by supporting a variety of storage media, so you can avoid costly hardware purchases to implement the solution. The product supports key storage technologies such as: Direct Attached Storage (DAS), Network Attached Storage (NAS), Storage Area Networks (SAN), Redundant Arrays of Independent Disks (RAID), tapes, USB and IEEE-1394 (FireWire) compliant storage devices, CDs, DVDs, removable drives (Floppy, Zip, etc.) and shared storage. Moreover, the product ensures that you maximize the space on these resources with four levels of compression.

Disk cloning and new disk deployment

Acronis True Image Echo Server can be used to clone an image onto multiple servers. For example, let's say a company purchased several servers and needs similar environments on each of them. Traditionally, the IT manager would install the operating system and programs on every server. With Acronis True Image Echo Server, the IT manager would configure a single server, then create a disk image of the system. That image can then be duplicated onto multiple servers.

If you need to upgrade the server hard disk drive, Acronis True Image Echo Server simplifies the task to few mouse clicks creating the exact copy of your old disk to a new one and adjusting partitions size to fit a new hard disk.

Volumes conversion

Acronis True Image Echo Server can back up and recover dynamic volumes.

Dynamic volume as is can be recovered over the same volume or unallocated space of a dynamic group. Acronis True Image Echo Server has necessary tools for any-to-any disks conversion in terms of basic disks and dynamic volumes of any type (simple, spanned, striped, mirrored or RAID 5). The tools are available in bootable program version as well. Having booted the Acronis environment, you can easily prepare the desired dynamic group on bare metal or a computer with non-Windows operating system.

1.2 New in Acronis True Image Echo Server

Backup

Backup and restore of 2+TB volumes

Encrypting backups with industry-standard AES cryptographic algorithm (key size 128, 192, 256 bit)

Multi-volume snapshot for databases spread on several disks

Control network bandwidth usage when backing up to FTP

Error handling: ignore bad sectors, silent mode (no pop-ups, continue on all errors)

Dual destination backup: local + network share

Support for VMware Consolidated backup

Archive bit reset (file-level backup only)

Generating time-based names for backup files

Recovery

Recovery of dynamic volumes

Recovery of system dynamic volumes on dissimilar hardware using Acronis Universal Restore or Acronis Active Restore

Scheduling

Schedule archive validation

Start every N hours within daily schedule

Start on free disk space change by the specified amount

Cloning a task

Notification via e-mail

Multiple e-mail addresses

From and Subject fields

Logon to incoming mail server

Operations with archives

Convert disk images to virtual disks for VMware, Microsoft, XenServer and Parallels virtual machines

Consolidate backup files (create a consistent copy of archive while deleting selected backups)

Explore archives (open in read-only mode any image or file-level backup)

Operations with hard disks

Convert basic disk to dynamic

Create dynamic volumes

CLI features

MBR restore

Backup to FTP server

Allow logs on net share

Merge unallocated space by moving partitions and create Acronis Secure Zone on the space

1.3 Supported file systems and storage media

1.3.1 Supported file systems

- FAT16/32
- NTFS
- Ext2/Ext3
- ReiserFS

-
- Reiser4
 - Linux SWAP
 - XFS
 - JFS
 - DFS

If a file system is not supported or is corrupted, Acronis True Image Echo Server can copy data using a sector-by-sector approach.



For XFS and JFS file systems the partition resizing feature is not supported.

1.3.2 Supported storage media

- Hard disk drives
- Networked storage devices such as Storage Area Networks (SANs) and Network Attached Storage (NAS)
- Tape libraries, autoloaders, SCSI tape drives
- IDE and SCSI RAID controllers of any level
- FTP-servers*
- CD-R/RW, DVD-R/RW, DVD+R (including double-layer DVD+R), DVD+RW, DVD-RAM**
- USB 1.0 / 2.0, FireWire (IEEE-1394) and PC card storage devices
- ZIP®, Jaz® and other removable media

* - Data recovery directly from an FTP-server will require the archive to consist of files no more than 2GB in size, so please note this during the backup image creation. It is recommended that you change the source computer firewall settings to disable the **Routing and Remote Access** Windows service. The previous versions of the software recommended for the target FTP-server the usage of passive mode for file transfers and usage of ports 20 and 21 at the source computer for both TCP and UDP protocols. The current version has no such limitations: you can use active or passive mode and any port, changing the default settings at **Options->Backup Options->Advanced settings**.

** - Burned rewritable discs cannot be read in Linux without kernel patch.

1.4 Technical support

As part of a purchased annual Support charge you are entitled to Technical Support as follows: to the extent that electronic services are available, you may electronically access at no additional charge, Support services for the Software, which Acronis shall endeavor to make available twenty four (24) hours a day, seven (7) days per week. Such electronic services may include, but are not limited to: user forums; software-specific information; hints and tips; bug fix retrieval via the internet; software maintenance and demonstration code retrieval via a WAN-accessible FTP server; and access to a problem resolution database via Acronis customer support system.

Support shall consist of supplying telephone or other electronic support to you in order to help you locate and, on its own, correct problems with the Software and supplying

patches, updates and other changes that Acronis, at its sole discretion, makes or adds to the Software and which Acronis makes generally available, without additional charge, to other licensees of the Software that are enrolled in Support.

Upon mutual agreement by both parties, Acronis shall:

(i) supply code corrections to you to correct Software malfunctions in order to bring such Software into substantial conformity with the published operating specifications for the most current version of the Software unless your unauthorized modifications prohibit or hamper such corrections or cause the malfunction;

or (ii) supply code corrections to correct insubstantial problems at the next general release of the Software.

More information about contacting Acronis Technical Support is available at the following link: <http://www.acronis.com/support/>

Chapter 2. Acronis True Image Echo Server installation and startup

2.1 System requirements

2.1.1 Minimum hardware requirements

Acronis True Image Echo Server requires the following hardware:

- Pentium processor or higher
- 512MB RAM
- FDD or CD-RW drive for bootable media creation
- Mouse (recommended).

2.1.2 Supported operating systems

Acronis True Image Echo Server

- Windows Professional 2000 SP4/ Professional XP SP3
- Windows Server 2000 /Advanced Server 2000 /Server 2003
- Windows XP Professional x64 Edition, Windows Server 2003 x64 Editions
- Windows Server 2008, Windows Server 2008 x64 Edition (except for the Acronis Active Restore feature)
- Windows Vista all Editions (except for the Acronis Active Restore feature)

Acronis Universal Restore (optional)

- Windows Professional 2000 SP4/XP Professional SP3
- Windows Server 2000 /Advanced Server 2000 /Server 2003/Server 2008
- Windows XP Professional x64 Edition, Windows Server 2003 x64 Editions, Windows Server 2008 x64 Edition
- Windows Vista all Editions


Acronis True Image Echo Server bootable version enables disk-level backup and recovery on a computer running any PC-based operating system.

2.2 Installing Acronis True Image Echo Server

To install Acronis True Image Echo Server, run the Acronis True Image Echo Server setup file.



If you have the trial version of Acronis True Image Echo Server installed on your system, you must uninstall it before installing the commercial version of the product.



Acronis True Image Echo Server Install Window

2.2.1 Installation of Acronis True Image Echo Server

Typical, **Custom** and **Complete** installation is available. Having pressed **Custom**, you can choose to install, besides the Acronis True Image Echo Server, **Rescue Media Builder** and **Bart PE plug-in**.

With **Rescue Media Builder** you can create bootable rescue disks or RIS packages (see details in *Chapter 9. Creating bootable media*). Installing the **Bootable Rescue Media Builder** will allow you to create bootable media, its ISO image or a bootable RIS package at any time from the main program window or running **Bootable Rescue Media Builder** on its own.

The widely used **Bart PE** utility provides a Windows-like operating environment invoked via removable bootable media. Applications are installed into Bart PE in the form of plug-ins. Choosing Bart PE plug-in installation (disabled by default) provides the ability to include Acronis True Image Echo Server into a Bart PE plug-in tab. The plug-in files will be placed into the component installation folder along with other program files.



When installed, Acronis True Image Echo Server creates a new device in the Device Manager list (**Control Panel -> System -> Hardware -> Device Manager -> Acronis Devices -> Acronis TrueImage Backup Archive Explorer**). Do not disable or uninstall this device, as it is necessary for connecting image backups as virtual disks (see *10.2.2 Mounting an image*).

2.2.2 Acronis Universal Restore installation

Acronis Universal Restore is an option for Acronis True Image Echo Server. It is purchased separately and installed from a separate setup file. Acronis Universal Restore has its own serial number that is required at installation.

Acronis Universal Restore can only be installed on a computer where at least one of the following Acronis components is installed:

Acronis True Image Echo Server

Bootable Media Builder.

Acronis Universal Restore can be installed on a networked computer either locally, by running the setup program, or remotely, using one of remote installation services such as Systems Management Server (a component of Microsoft Windows NT BackOffice program package).

After installation, Acronis Universal Restore automatically plugs in one or more of above program components. Acronis True Image Echo Server name, displayed in its main window, changes to **Acronis True Image Echo Server with Universal Restore**.

2.3 Extracting Acronis True Image Echo Server components

When installing Acronis True Image Echo Server, you can save the setup (.msi) file on a local or network drive. This will help when modifying or recovering the existing product installation.

To save the setup file:

- run the Acronis True Image Echo Server setup file
- in the Install Menu, right-click on the program name and select **Extract**
- select a location for the setup file and click **Save**.

2.4 Running Acronis True Image Echo Server

You can run Acronis True Image Echo Server in Windows by selecting **Start -> Programs -> Acronis -> Acronis True Image Echo Server -> Acronis True Image Echo Server** or clicking the appropriate shortcut on the desktop.

If your operating system fails to load, you can run Acronis Startup Recovery Manager. However, this must be activated *prior* to use; see *3.4 Acronis Startup Recovery Manager* to learn more about this procedure. To run the program, press F11 during the server bootup when you see a corresponding message that tells you to press that key. Acronis True Image Echo Server will be run in the standalone mode, allowing you to recover the damaged partitions.

If your disk data is totally corrupted and you cannot boot (or if you have not activated Acronis Startup Recovery Manager), load the standalone Acronis True Image Echo Server version from the bootable media (created by you using Rescue Media Builder) or RIS-server. Then you will be able to restore the disk from a previously created image.

2.5 Removing Acronis True Image Echo Server

You can remove Acronis True Image Echo Server by selecting **Control panel -> Add or remove programs -> <Acronis True Image Echo Server> -> Remove**. Then follow instructions on the screen. You may have to reboot your computer afterwards to complete the task.

In case you remove Acronis True Image Echo Server from the system, there is an option to keep the Acronis Secure Zone along with its contents (which will enable data recovery on booting from bootable media) or remove Acronis Secure Zone.

Chapter 3. General information and proprietary Acronis technologies

3.1 The difference between file archives and disk/partition images

A backup archive is a file or a group of files (also called in this guide “backups”), that contains a copy of selected files/folders data or a copy of all information stored on selected disks/partitions.

When you back up files and folders, only the data, along with the folder tree, is compressed and stored.

Backing up disks and partitions is performed in a different way: Acronis True Image Echo Server saves a sector-based snapshot of the disk, which includes the operating system, registry, drivers, software applications and data files, as well as system areas hidden from the user. This procedure is called “creating a disk image,” and the resulting backup archive is often called a disk/partition image.



Acronis True Image Echo Server stores only those hard disk parts that contain data (for supported file systems). Further, it does not back up swap file information (pagefile.sys) and hiberfil.sys (a file that keeps RAM contents when the computer goes into hibernation). This reduces image size and speeds up image creation and restoration.



A partition image includes all files and folders independent of their attributes (including hidden and system files), boot record, FAT (file allocation table), root and the zero track of the hard disk with master boot record (MBR).



A disk image includes images of all disk partitions as well as the zero track with the master boot record (MBR).

All Acronis True Image Echo Server archives files have a “.tib” extension by default.

It is important to note that you can restore files and folders not only from file archives, but from disk/partition images, too. To do so, mount the image as a virtual disk (see *10.2.2 Mounting an image*) or start the image restoration and select **Restore specified files or folders**.

3.2 Full, incremental and differential backups

Acronis True Image Echo Server can create full, incremental and differential backups.

A **full backup** contains all data at the moment of backup creation. It forms a base for further incremental or differential backup or is used as a standalone archive. A full backup has the shortest restore time as compared to incremental or differential ones.

An **incremental backup** only contains data changed since the last full or incremental backup creation. Therefore, it is smaller and takes less time to create. However, since it does not contain all data needed to restore an image, *all* the previous incremental backups *and* the initial full backup are required for restoration.

A **differential backup** creates an independent file containing all changes since the last full archive. Generally, data from a differential backup will be restored faster than an incremental backup, as it does not have to process through a long chain of previous backups.

A standalone, full backup could be an optimal solution if you often roll back the system to the initial state (for example, systems in a gaming club or Internet café where you need to undo changes made by the guests). In this case, you need not re-create the initial full image, so the backup time is not crucial and the restore time will be minimal.

Alternatively, if you are interested in saving only the most current data state to be able to restore it in case of system failure, consider the differential backup. It is particularly effective if your data changes tend to be little as compared to the full data volume.

An incremental backup is most useful when you need frequent backups and possibility to roll back to any one of multiple stored states. For example, let's say you create a full backup once a month. If you then create an incremental backup each day of a month, you will get the same result as if you created full backups every day. However, the cost in time and disk space (or removable media usage) will be as little as one tenth as much.

It is important to note that the above arguments are just examples for your information. Feel free to make up your own backup policy in accordance with your specific tasks and conditions. Acronis True Image Echo Server is flexible enough to meet any real-life demands.



An incremental or differential backup created after a disk is defragmented might be considerably larger than usual. This is because the defragmentation program changes file locations on disk and the backups reflect these changes. Therefore, it is recommended that you re-create a full backup after disk defragmentation.

3.3 Acronis Secure Zone®

The Acronis Secure Zone is a special partition for storing archives on the computer system itself. Certain Windows applications, such as Acronis disk management tools, can access the zone. In the Acronis True Image Echo Server Wizards' windows the zone is listed along with all partitions available for storing archives.

A consistent external copy of archives, saved on Acronis Secure Zone, can be created on a network share using dual destination backup feature. See details in *5.3.12 Dual destination backup*.

Acronis Secure Zone is always available for archive creation as long as there is space for the backup file. If there is not enough space, older archives will be deleted to create space.

Acronis True Image Echo Server uses the following approaches to free up space in the Acronis Secure Zone:

- If there is not enough free space in the zone to create a backup, the program deletes the oldest full backup with all subsequent incremental/differential backups.
- If there is only one full backup (with subsequent incremental/differential backups) left and a full backup is in progress, then the old full backup and incremental/differential backups are deleted.
- If there is only one full backup left, and an incremental or differential backup is in progress, you will get an error message telling you there is a lack of available space. In that case, you will have to either re-create the full backup or increase the size of the Acronis Secure Zone.

You can also manually consolidate or remove unnecessary backups from Acronis Secure Zone (See *8.4 Managing backups in the Acronis Secure Zone*)

Acronis Secure Zone contents can be viewed directly from Windows Explorer. Open **My Computer** (Start -> My computer, or Start -> Run... -> explorer /n, /e, /select, c:\) and double-click on the **Acronis Secure Zone** icon. In the window that opens, all backup archives stored in the zone along with their creation dates will be listed. However, viewing backup archive contents, backup restoration, consolidation, and deletion can be performed from Acronis True Image Echo Server only. For more information, see *8.4 Managing backups in the Acronis Secure Zone*.

For information on how to create, resize or delete Acronis Secure Zone see *Chapter 8. Managing the Acronis Secure Zone*.

You can back up data automatically on a schedule (see *Chapter 7. Scheduling tasks*), and not worry about zone overflow issues. However, if you keep long chains of incremental backups, it is a good practice to check the zone free space periodically. To do so, start the **Manage Acronis Secure Zone** wizard and see the zone free space that is displayed on the wizard's second page. To do so, start the **Manage Acronis Secure Zone** wizard and check the zone free space, or manually remove or consolidate unnecessary backups.

For information on how to create, resize or delete Acronis Secure Zone, or manage Acronis Secure Zone backup archives using this wizard, see *Chapter 8. Managing the Acronis Secure Zone*.

In case you remove Acronis True Image Echo Server from the system, there is an option to keep the Acronis Secure Zone along with its contents (which will enable data recovery on booting from bootable media) or remove Acronis Secure Zone.



The Acronis Secure Zone should not be the only location where a backup is stored. Should the disk have a physical failure, the Acronis Secure Zone could be lost. This is particularly critical for backups of servers; the Acronis Secure Zone should only be one part of an overall backup strategy.

3.4 Acronis Startup Recovery Manager

3.4.1 How it works

The Acronis Startup Recovery Manager enables starting Acronis True Image Echo Server without loading the operating system. If the operating system won't load, you can run Acronis True Image Echo Server by itself to restore damaged partitions. Unlike booting from the Acronis removable media or RIS server, you will not need a separate media or network connection to start Acronis True Image Echo Server. It is especially handy for mobile users who need to run a server operating system on their laptop.

3.4.2 How to use

To be able to use Acronis Startup Recovery Manager at boot time, prepare as follows:

1. Install Acronis True Image Echo Server or Acronis True Image Agent on a computer.
2. Activate Acronis Startup Recovery Manager. To do so, click **Activate Acronis Startup Recovery Manager** and follow the Wizard's instructions.



When Acronis Startup Recovery Manager is activated, it overwrites the master boot record (MBR) with its own boot code. If you have any third-party boot managers installed, you will have to reactivate them after activating the Startup Recovery Manager. For Linux loaders (e.g. LiLo and GRUB), you might consider installing them to a Linux root (or boot) partition boot record instead of MBR before activating Acronis Startup Recovery Manager.

Here's an example of how you would use this feature. If failure occurs on a computer, turn on the computer and press F11 when you see the "Press F11 for Acronis Startup Recovery Manager" message. This will run a standalone version of Acronis True Image Echo Server that only slightly differs from the complete version. For information on restoring damaged partitions, see *Chapter 6. Restoring the backup data*.



Be careful! Disk letters in standalone Acronis True Image Echo Server might sometimes differ from the way Windows identifies drives. For example, the D: drive identified in the standalone Acronis True Image might correspond to the E: drive in Windows.

3.5 Acronis Active Restore

With this feature you can boot the OS on a crashed computer before the system is completely restored from an image and start work seconds after the restoration is launched. The restoration will be continued in the background.

3.5.1 Limitations in using Acronis Active Restore

1. Acronis Active Restore is currently available for images located in the Acronis Secure Zone only.
2. Acronis Active Restore does not support images of Windows Vista and Windows Server 2008. If any Vista or Windows Server 2008 edition is detected in an image, the Active Restore option will not appear.
3. Acronis Active Restore does not work if the image contains dynamic disks and volumes.
4. Acronis Active Restore cannot be used if the image contains no operating system (a logical partition or disk image) or when restoring file archives.

3.5.2 How it works

When the restoration procedure is started, Acronis True Image Echo Server:

1. Finds the sectors in the image which contain system files, and restores these sectors first. First the OS is restored and can be started very quickly. Having started the OS, the user sees the folder tree with files, though file contents still is not recovered. Nevertheless, the user can start working.
2. Next, the application writes on the hard disk its own drivers, which intercept system queries to the files. When the user attempts to open files or launch applications, the drivers receive the system queries and restore the sectors that are necessary for the requested operation.
3. At the same time, Acronis True Image Echo Server proceeds with the complete sector-by-sector image restoration in the background. However, the requested sectors have the highest priority.

Finally, the image will be fully restored even if the user performs no actions at all. But if you choose to start working as soon as possible after the system failure, you will gain at least several minutes, considering that restoration of a 10-20GB image (most common image size) takes about 10 minutes. The larger the image size, the more time you save.

3.5.3 How to use

To be able to use Acronis Active Restore, prepare your system this way:

1. Install Acronis True Image Echo Server.

-
2. Create the Acronis Secure Zone on the server hard disk (see *Chapter 8. Managing the Acronis Secure Zone*).
 3. Activate Acronis Startup Recovery manager (see *3.4 Acronis Startup Recovery Manager*) and create bootable media or RIS package with Acronis True Image Echo Server (see *Chapter 9. Creating bootable media*).
 4. Back up (image) the server's system disk to Acronis Secure Zone (see *5.2 Backing up disks and partitions (image backup)*). You can back up other disks/partitions as well, but the system image is mandatory.



When performing Active Restore, the current Acronis True Image Echo Server version always restores the entire system disk. Therefore, if your system disk consists of several partitions, all of them must be included in the image. Any partitions which are missing from the image will be lost.

If failure occurs, boot the server from the bootable media, or RIS server, or using F11. Start the recovery procedure (see *6.3 Restoring disks/partitions or files from images*), select the system disk image from Acronis Secure Zone, choose **Use Active Restore** and in the next window click **Proceed**. In a few seconds the computer will reboot to the restored system. Log in and start work – no additional reboots or other actions are required.

You can perform Active Restore running Acronis True Image Echo Server in Windows operating systems as well. However, it is mandatory to have bootable media in case Windows cannot boot.

3.6 Acronis Universal Restore

3.6.1 Acronis Universal Restore purpose

A system disk image can be deployed easily on the hardware where it was created or to identical hardware. However, if you change a motherboard or use another processor version — a likely possibility in case of hardware failure — the restored system could be unbootable. An attempt to transfer the system to a new, much more powerful computer will usually produce the same unbootable result because the new hardware is incompatible with the most critical drivers included in the image.

Using Microsoft System Preparation Tool (Sysprep) does not solve this problem, because Sysprep permits replacing drivers only for Plug-and-Play devices (sound cards, network adapters, video cards etc.). As for system Hardware Abstraction Layer (HAL) and mass storage device drivers, they must be identical on the source and the target computers (see Microsoft Knowledge Base, articles 302577 and 216915).

Acronis Universal Restore technology provides an efficient solution for hardware-independent system restoration by replacing the crucial Hardware Abstraction Layer (HAL) and mass storage device drivers.

Acronis Universal Restore is applicable for:

1. Instant recovery of a failed system on different hardware
2. Hardware-independent cloning and deployment of operating systems
3. Real-to-virtual and virtual-to-real computer migration for system recovery, test and other purposes.

3.6.2 Acronis Universal Restore general principles

1. Automatic HAL and mass storage drivers selection

Acronis Universal Restore searches the Windows default driver storage folders (in the image being restored) for HAL and mass storage device drivers and installs drivers that better fit the target hardware. You can specify a custom driver repository (a folder or folders on a network drive or CD) which will also be used for drivers search.



The Windows default driver storage folder is determined in the registry key `HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\Current version\DevicePath`. This storage folder is usually `WINDOWS/inf`.

2. Manual selection of mass storage device driver

If the target hardware has a specific mass storage controller (such as a SCSI, RAID, or Fibre Channel adapter) for the hard disk, you can install the appropriate driver manually, bypassing the automatic driver search-and-install procedure.

3. Installing drivers for plug and play devices

Acronis Universal Restore relies on built-in plug and play discovery and configuration process to handle hardware differences in devices that are not critical for the system start, such as video, audio and USB. Windows takes control over this process during the logon phase, and if some of the new hardware is not detected, you will have a chance to install drivers for it later manually.

3.6.3 Acronis Universal Restore and Microsoft Sysprep

Acronis Universal Restore is *not* a system preparation tool. You can apply it to any system image created by Acronis products, including images prepared with Microsoft System Preparation Tool (Sysprep). The following is an example of using both tools on the same system.

Acronis Universal Restore does not strip security identifier (SID) and user profile settings in order to run the system immediately after recovery without re-joining the domain or re-mapping network user profiles. If you are going to change the above settings on a recovered system, you can prepare the system with Sysprep, image it and restore, if need be, using Acronis Universal Restore.

3.6.4 Limitations in using Acronis Universal Restore

1. The system recovered by Acronis Universal Restore might not start if the partition structure in the image or the target disk partitioning does not coincide with that of the source disk. As a result, the loader, restored from the image, will point to the wrong partition and the system will not boot or will malfunction.

Such might be the case if you:

- image only selected partitions but not the entire source disk



Keep in mind, that the source disk may have a hidden maintenance partition created by the computer vendor. Therefore, if you check each partition for backup instead of checking the disk, this hidden partition will not be included into the image.

- restore not the entire source disk, but only the selected partitions. In some cases, especially if your system resides on a partition other than the first, this can confuse the loader and prevent the restored system from startup.

To avoid the problem, we recommend that you image and restore the entire system disk.

2. The Acronis Universal Restore option does not work if a computer is booted with Acronis Startup Recovery Manager (using F11) or the backup image is located in Acronis Secure Zone. This is because Acronis Startup Recovery Manager and Acronis Secure Zone are primarily meant for instant data recovery on the same computer.

3.6.5 Getting Acronis Universal Restore

Acronis Universal Restore is an add-on to Acronis True Image Echo Server. It is purchased separately, has its own license, and is installed from a separate setup file.

Let's assume for a moment that you own Acronis True Image Echo Server but have not purchased Acronis Universal Restore. When you create a task for restoring a Windows system disk and select a target disk (either physical or virtual) in the Restore Data Wizard, the program compares crucial for the system start devices found in the image registry and the target computer registry. If the chipset, motherboard or mass storage device are different, and therefore there is a risk that the system cannot boot, you will be prompted whether you want to buy Acronis Universal Restore. To buy the option, follow the link: <http://www.acronis.com/enterprise/products/ATISWin/universal-restore.html>

If you already have Acronis Universal Restore, the prompt will not come up and you will have an option to enable Acronis Universal Restore later in the Restore Data Wizard.

3.7 Backing up to tape drives

Acronis True Image Echo Server supports SCSI tape drives. It can store backups on the tape and restore data from the tape, store large backups to multiple tapes, and append incremental/differential changes to a tape with the existing archives.

If a SCSI tape drive is connected to the computer with Acronis True Image Echo Server the list of devices available for backup storage will be extended with a name corresponding to the drive type.

Backup and restore on the tape proceed in the same way as with other devices, with the following exceptions.

1. A full backup can be stored on an empty tape only. If you use tape that already contains data, its contents will be overwritten.
2. In case you want to keep more than one archive on the tape, for example, back up two disks separately, choose incremental backup mode instead of a full backup when you create an initial backup for the second disk. In other situations, incremental backup is used for appending changes to the previously created archive.
3. You do not have to provide filenames for backups.

You might experience short pauses that are required to rewind the tape.

To enable backup to a locally attached tape device with Acronis True Image Echo Server:

1. Install Acronis True Image Echo Server.
2. Attach the tape device to the computer.
3. If the tape contains data, its contents will be overwritten on prompt. You have an option to disable prompts, see *5.3.13 Additional settings*.
4. When creating a backup task, you will be able to select the tape device from the list of destination devices. Filenames for backups are not needed when backing up to tape.

5. As soon as the tape is full, a dialog window with a request to insert a new tape will appear.



Low-quality or old tape, as well as dirt on the magnetic head, might lead to pauses that can last up to several minutes.



Implementation notice

Due to the wide variety of tape libraries and configuration complexity, for detailed information on how to implement Acronis True Image Echo Server with tape drives please contact Acronis support specialists.

3.7.1 Restoring data from archives located on tape devices

Data recovery from archives located on tape devices is performed in the same way as with other storage devices.

When recovering, you start the restore wizard, select the local tape device or tape device under the backup server, select the archive and the backup to restore data from.

You will be prompted to insert tapes required for restoring data from the selected backup.

3.8 Viewing disk and partition information

You can change the way data is represented in all schemes you see in various wizards.

To the right are three icons: **Arrange Icons by**, **Choose Details** and **i (Display the properties of the selected item)**, the last duplicated in the context menu invoked by right-clicking objects.

To sort messages by a particular column, click the header (another click will switch the messages to the opposite order) or **Arrange Icons by** button and select the column.

To select columns to view, right-click the headers line or left-click the **Choose Details** button. Then flag the columns you want to display.

If you click the **i (Display the properties of the selected item)** button, you will see the selected partition or disk properties window.

This window contains two panels. The left panel contains the properties tree and the right describes the selected property in detail. The disk information includes its physical parameters (connection type, device type, size, etc.); partition information includes both physical (sectors, location, etc.), and logical (file system, free space, assigned letter, etc.) parameters.

You can change the width of a column by dragging its borders with the mouse.

3.9 Changing Acronis temporary folder path


By default, Acronis True Image Echo Server saves its temporary files in a system directory designated for temporary files. You will need to create a new system variable for saving them in other location: right-click on **My Computer** and choose "Properties". In the box that opens, click the "Advanced" tab. Next, click the button "Environment Variables". Create a system variable "**ACRONIS_SNAPSHOT_TMP_DIR**" and specify the location for Acronis temporary files.

Chapter 4. Using Acronis True Image Echo Server

Acronis True Image Echo Server supports the GUI mode, the command-line mode, and can be used to execute XML scripts. Here we describe the operations available in the GUI mode, which provides the widest functionality. For console commands and scripting please see *Chapter 15. Command-line mode and scripting*.

4.1 Main program window

The main program window contains the menu, the toolbar, the sidebar and the main area. The sidebar features a pane for selecting task category, the **Tools** and **Help** panes. The main area displays operation icons or tasks depending on the category selected.



By default, the program displays operations included in the **Backup and Recovery** category. Operation icons are divided into three groups.

The **Task** group contains the following operations:

- **Backup** – create a backup archive
- **Recovery** – restore data from a previously created archive

The **Manage Tasks** group contains the following operations:

- **Tasks** – schedule backup or archive validation tasks on your computer and manage them
- **Logs** – open the Log Viewer window

The **Tools** group contains the following items:

-
- **Explore and Validate Backup Archives** – explore file-level archives, mount disk/partition images as virtual drives, run the archive integrity checking procedure
 - **Manage Hard Disks** – clone disk (i.e. transfer the OS, applications and data from the old disk to the new one) or mark out partitions on a new hard disk added for data storage with the OS and applications kept on the old one, convert basic disks to dynamic and create dynamic volumes
 - **Activate Acronis Startup Recovery Manager** – activate the boot restoration manager (F11 key)
 - **Manage System Restore** – turn on/off Microsoft Windows System Restore tool and set its options directly from Acronis True Image Echo Server
 - **Create Bootable Rescue Media** – run the bootable media creation procedure

Program menu

The program menu bar features the **Operations**, **View**, **Tools** and **Help** items.

The **Operations** menu contains a list of the available operations, including scheduling tasks.

The **View** menu contains items for managing the program window look:

- **Toolbars** – contains commands that control toolbar icons
- **Common Task Bar** – enables/disables the sidebar
- **Status Bar** – enables/disables the status bar

The **Tools** menu contains the following items:

- **Manage Acronis Secure Zone** – create, delete and resize a special partition for storing archives (Acronis Secure Zone)
- Activate Acronis Startup Recovery Manager – activate the boot restoration manager (F11 key)
- **Explore Backup Archive** – explore file-level archives or mount disk/partition images as virtual drives
- **Validate Backup Archive** – run the archive integrity checking procedure
- **Consolidate archive** – applicable for archives containing more than one backups. This will create a consistent copy of the archive with an option to exclude backups that are no more needed
- **Convert Backup to Virtual Disk** - convert a disk image, created with the program (.tib), to a virtual disk file of the type you select (.vmdk, .vhd, .hdd)
- **Create Bootable Rescue Media** – run the bootable media creation procedure
- **Dynamic Volume Creation Wizard** – create dynamic volumes on basic or dynamic disks
- **Show Log** – open the Log Viewer window
- **Options** – open a window for editing default backup/restore options, setting text appearance (fonts), configuring e-mail or Windows pop-up notifications etc.

The **Help** menu is used to view help and obtain information about Acronis True Image Echo Server.

Most of the operations are represented two or even three times in different window areas, providing several ways to select them for more convenience. For example, you can start the necessary operation or tool by clicking its icon in the main area or by selecting the same item from the **Operations** or **Tools** menu.

Status bar

There is a status bar divided into two parts at the bottom of the main window. The left side briefly describes the selected operation; the right side indicates operation progress and results. If you double-click on the operation results, you will see the log window.

Taskbar notification area icon

During most of the operations, a special indicator icon appears in the Windows taskbar notification area. If you mouse over the icon, you will see a tool tip indicating the operation's progress. This icon doesn't depend on the main program window being open. It is present for background execution of scheduled tasks as well.

4.2 Available operations

You can perform the following operations.

Operation	How to access
Back up and Recover	
Back up and restore data, including system disks/partitions	Click Backup or Recovery , then follow the wizard's instructions. See details in <i>Chapter 5. Creating backup archives</i> and <i>Chapter 6. Restoring the backup data</i> .
Browse logs of Acronis True Image Echo Server operation	Click Logs in the Manage Tasks group or select the Show Log tool on the sidebar to navigate to the Event Log window. See details in <i>11.3 Viewing logs</i> .
Set up default backup or restore options, such as system/network resources usage, before/after backup commands etc.	Select Tools -> Options -> Default backup options or Default restoration options and make settings. See details in <i>5.3 Setting backup options</i> and <i>6.4 Setting restore options</i> .
Set up default parameters for sending notifications about Acronis True Image Echo Server operation and tracing this operation in Windows Application Event Log	Select Tools -> Options -> Notifications or Event tracing and make settings. See details in <i>Chapter 11. Notifications and event tracing</i> .
Scheduling Tasks	
Schedule backup and archive validation operations	Click Tasks in the Manage Tasks group or select the Task Scheduling category on the sidebar to navigate to the Scheduled Tasks window. Then click the Create button on the toolbar and follow the wizard's instructions. See details in <i>Chapter</i>

7. Scheduling tasks.

Run, stop, edit, clone, rename, delete backup and archive validation tasks

Click **Tasks** in the **Manage Tasks** group or select the **Task Scheduling** category on the sidebar to navigate to the Scheduled Tasks window. See details in *7.2 Managing scheduled tasks*.

Archives Management

Explore any archive's contents and restore individual files from any archive

Select **Tools -> Explore Backup Archive** and follow the wizard's instructions. See details in *10.2.1 Exploring an archive*

Validate backup archives wherever they reside, be it local, network or removable media

Select **Tools -> Validate Backup Archive**, then follow the wizard's instructions. See details in *10.1 Validating backup archives*.

Consolidate backup files inside an archive

Select **Tools -> Consolidate archive**, then follow the Wizard's instructions. See details in *10.3 Consolidating backup*.

Convert disk images to virtual disk files of the type you select (.vmdk, .vhd, .hdd)

Select **Tools -> Convert backup to Virtual Disk** and follow the wizard's instructions. See details in *12. 4 Converting disk images to virtual disks*

Mount partitions' images to explore and modify their contents, or to restore individual files

Select **Operations -> Mount Image** and follow the wizard's instructions. See details in *10.2.2 Mounting an image*.

Unmount previously mounted partition images

Select **Operations -> Unmount Image** and follow the wizard's instructions. See details in *10.2.3 Unmounting an image*.

Hard Disk Management

Manage Acronis Secure Zone (create, delete, resize, remove or change password)

Click **Manage Acronis Secure Zone**, then follow the wizard's instructions. See details in *Chapter 8. Managing the Acronis Secure Zone*.

Activate Acronis Startup Recovery Manager

Click **Activate Acronis Startup Recovery Manager**, then follow the wizard's instructions. See details in *3.4 Acronis Startup Recovery Manager*.

Create a dynamic volume

Select **Tools -> Dynamic volume creation wizard**, then follow the Wizard's instructions. See details in *6.5.1 Creating dynamic volumes*.

Transfer the system to a new hard disk

See *Chapter 13. Transferring the system to a new disk*.

Format partitions on a new hard disk

See *Chapter 14. Adding a new hard disk.*

Other Tools

Create bootable rescue media, its ISO or RIS package

See *Chapter 9. Creating bootable media.*

Turn on/off Windows System Restore tool

See *11.5 Managing System Restore.*

Some of the above operations can be executed in command-line mode. For more information on Acronis True Image Echo Server command-line mode see *15.1 Working in the command-line mode.*

Chapter 5. Creating backup archives


To be able to restore the lost data or roll back your system to a predetermined state, you should first create a data or entire system backup file.

If you are not concerned about restoration of your operating system along with all settings and applications, but plan to keep safe only certain data (the current project, for example), choose file/folder backup. This will reduce the archive size, thus saving disk space and possibly reducing removable media costs.

Backing up the entire system disk (creating a disk image) takes more disk space but enables you to restore the system in minutes in case of severe data damage or hardware failure. Moreover, the imaging procedure is much faster than copying files, and may significantly speed the backup process when it comes to backing up large volumes of data (see details in *3.1 The difference between file archives and disk/partition images*).

5.1 Backing up files and folders (file backup)


1. Start the **Create Backup Wizard** by clicking on the backup operation icon in the main program window.
2. Select **My Data**.
3. From the tree pane, select files and folders to back up. You can select a random set of files, folders, partitions, disks and even computers.



In order to restore your operating system, you must image the system disk or partition; a file-based backup is not sufficient for the operating system restore.

4. You can exclude specific files from a backup by setting filters for the types of files you do not wish to back up. For example, you may want to exclude hidden and system files and folders or files with **.~**, **.tmp** and **.bak** extensions.

You can also apply custom filters, using the common Windows masking rules. For example, to exclude all files with extension .exe, add ***.exe**. **My???.exe** will exclude all .exe files with names consisting of five symbols and starting with "my".



All of these settings will take effect for the current task. For information on how to set the default filters that will be called each time you create a file backup task, see *5.3.2 Source files exclusion*.

5. Select the name and location of the archive.

If you are going to create a full backup, type the file name in the **File Name** line, or use the file name generator (a button to the right of the line). If you select an existing full backup, it will be overwritten.


Including [date] in the backup file name will add to the name the time and date of the backup creation formatted as <DD-Month-YYYY HH:MM:SS>. Example: C:\MyBackup[date].tib.

If you are going to create an incremental backup (see *3.2 Full, incremental and differential backup*), select the latest full or incremental backup you have.



In fact, if all incremental backup files are stored together with the basic full backup, it doesn't matter which one you select, as the program will recognize them as a single archive. If you stored the files on several removable disks, you must provide the latest archive file; otherwise, restoration problems might occur.

If you are going to create a differential backup, select the full backup which will be a base, or any of the existing differential backups. Either way, the program will create a new differential backup.



The “farther” you store the archive from the original folders, the safer it will be in case of data damage. For example, saving the archive to another hard disk will protect your data if the primary disk is damaged, but won’t be useful if the computer is destroyed in a fire or flood. Data saved to a network disk, ftp server or removable media will survive even if all your local hard disks are down. You can also use Acronis Secure Zone (see details in *3.3 Acronis Secure Zone*) for storing backups. In this case, you need not provide the file name.


When backing up to Acronis Secure Zone, you have an option of dual destination backup. If enabled, the program will automatically place a copy of your backup archives on a local drive or network share as well as Acronis Secure Zone. See details in *5.3.12 Dual destination backup*.

Dynamic volumes are fully supported as a backup destination place. Acronis True Image Echo Server can access backup archives, created on dynamic volumes, in standalone (rescue) mode as well as under Windows control.



See notes and recommendations for using the FTP server in *1.3.2 Supported storage media*.

6. Select whether you want to create a full, incremental or differential backup. If you have not backed up the selected files/folders yet, or the full archive seems too old to append incremental changes to it, choose full backup. Otherwise it is recommended that you create an incremental or differential backup (see *3.2 Full, incremental and differential backup*).




7. Select the backup options (that is, backup file splitting, compression level, password protection, pre/post backup commands etc.). You may select **Use default options** or **Set the options manually**. If the latter is the case, the settings will be applied only to the current backup task. Alternatively, you can edit the default options from the current screen. Then your settings will be saved as the defaults. See *5.3 Setting backup options* for more information.

8. Provide a comment for the archive. This can help prevent you from restoring the wrong files. However, you can choose not to make any notes. The backup file size and creation date are automatically appended to the description, so you do not need to enter this information.

9. At the final step, the backup task summary is displayed. Up to this point, you can click **Back** to make changes in the created task. Clicking **Proceed** will launch the task.

10. The task progress will be shown in a special window. You can stop the procedure by clicking **Cancel**.

You can also close the progress window by clicking **Hide**. The backup creation will continue, but you will be able to start another operation or close the main program window. In the latter case, the program will continue working in the background and will automatically close once the backup archive is ready. If you prepare some more backup operations, they will be queued after the current one.



You can adjust the backup process priority. To do so, click on the process icon in the System Tray and select Low, Normal, or High priority from the menu that appears. For information on how to set the default priority, see *5.3.6 Backup performance*.


11. You may want to see the log when the task is completed. To view the log, click the **Show Operation Logs** button on the toolbar.



If you burn an archive to multiple removable media, be sure to number them, since you will have to insert them in order during the restoration.

5.2 Backing up disks and partitions (image backup)

1. Start the **Create Backup Wizard** by clicking on the backup operation icon in the main program window.
2. Select **My Computer**.
3. Select disks, partitions or dynamic volumes to back up. You can select a random set of disks, partitions and dynamic volumes.



4. Select the name and location of the archive.

If you are going to create a full backup, type the file name in the **File Name** line, or use the file name generator (a button to the right of the line). If you select an existing full backup, it will be overwritten.

Including [date] in the backup file name will add to the name the time and date of the backup creation formatted as <DD-Month-YYYY HH:MM:SS>. Example: C:\MyBackup[date].tib.

If you are going to create an incremental backup (see 3.2 *Full, incremental and differential backup*), select the latest full or incremental backup you have.



In fact, if all incremental backup files are stored together with the basic full backup, it doesn't matter which one you select, as the program will recognize them as a single archive. If you stored the files on several removable disks, you must provide the latest archive file; otherwise, restoration problems might occur.

If you are going to create a differential backup, select the full backup which will be a base, or any of the existing differential backups. Either way, the program will create a new differential backup.

The "farther" you store the archive from the original partition, the safer it will be in case of data damage. For example, saving the archive to another hard disk will protect your data if your primary disk is damaged. Data saved to a network disk, ftp server or removable media will survive even if all your local hard disks are down. You can also use Acronis Secure Zone (see details in 3.3 *Acronis Secure Zone*) for storing backups. In this case, you need not provide the file name.

When backing up to Acronis Secure Zone, you have an option of dual destination backup. If enabled, the program will automatically place a copy of your backup archives on a local drive or network share. See details in 5.3.12 *Dual destination backup*.

Dynamic volumes are fully supported as a backup destination place. Acronis True Image Echo Server can access backup archives, created on dynamic volumes, in standalone (rescue) mode as well as under Windows control.



See notes and recommendations for using the FTP server in *1.3.2 Supported storage media*.

5. Select whether you want to create a full or incremental backup. If you have not backed up the selected disks/partitions yet, or the full archive seems too old to append incremental changes to it, choose full backup. Otherwise it is recommended that you create an incremental or differential backup (see *3.2 Full, incremental and differential backup*).
6. Select the backup options (that is, backup file splitting, compression level, password protection, pre/post backup commands etc.). You may **Use default options** or **Set the options manually**. If the latter is the case, the settings will be applied only to the current backup task. Alternatively, you can edit the default options from the current screen. Then your settings will be saved as the defaults. See *5.3 Setting backup options* for more information.
7. Provide a comment for the archive. This can help prevent you from restoring the wrong disk or partition. However, you also can choose not to make any notes. The backup file size and creation date are automatically appended to the description, so you do not need to enter this information.
8. At the final step, the backup task summary is displayed. Up to this point, you can click **Back** to make changes in the created task. Clicking **Proceed** will launch the task.
9. The task progress will be shown in a special window. You can stop the procedure by clicking **Cancel**.

You can also close the progress window by clicking **Hide**. The backup creation will continue, but you will be able to start another operation or close the main program window. In the latter case, the program will continue working in the background and will automatically close once the backup archive is ready. If you prepare some more backup operations, they will be queued after the current.



You can adjust the backup process priority. To do so, click on the process icon in the System Tray and select Low, Normal, or High priority from the menu that appears. For information on how to set the default priority, see *5.3.6 Backup performance*.

10. You may want to see the log when the task is completed. To view the log, click the **Show Operation Logs** button on the toolbar.




If you burn an archive to multiple removable media, be sure to number them, since you will have to insert them in order during the restoration.

5.3 Setting backup options

To view or edit the default backup options, select **Tools -> Options -> Default Backup Options** from the main program menu.

You can edit the default (or set the temporary) backup options while creating a backup task as well.



5.3.1 Archive protection

Password

The preset is **no password**.

An archive can be protected with a password. To protect the archive data from being accessed by anybody except you, enter a password and its confirmation into the text fields. A password should consist of at least eight symbols and contain both letters (in the upper and lower cases preferably) and numbers to make it more difficult to guess.

If you try to restore data from a password-protected archive, or append an incremental/differential backup to such an archive, Acronis True Image Echo Server will ask for the password in a special window, allowing access only to authorized users.

Passwords cannot be set for archives created in the Acronis Secure Zone. To protect such archives, set a password for the zone itself.

Encryption

The preset is **128 bit**.

Once the password has been set, you can choose to encrypt the backup for advanced security with industry-standard AES cryptographic algorithm. The password is used to generate a key which may differ in length. There are 4 choices: no encryption, 128, 192 and 256-bit encryption. The more the key size, the longer time to cipher and the greater is your data security.

5.3.2 Source files exclusion

By default, all files from the selected folders will be included in the archive.

You can set default filters for the specific types of files you do not wish to back up. For example, you may want hidden and system files and folders, as well as files with **.~**, **.tmp** and **.bak** extensions, not to be stored in the archive.

You can also apply custom filters, using the common Windows masking rules. For example, to exclude all files with extension **.exe**, add ***.exe**. **My???.exe** will exclude all **.exe** files with names consisting of five symbols and starting with "my".

This option is effective for file/folders backup only. When creating a disk/partition image, you cannot filter out any files.

5.3.3 Pre/post commands

You can specify commands or batch files to be automatically executed before and after the *backup procedure*. For example, you may want to remove some tmp files from the disk before starting backup or configure a third-party antivirus product to be started each time before the backup starts. Click **Edit** to open the **Edit Command** window where you can easily input the command, its arguments and working directory or browse folders to find a batch file.

The program does not support interactive commands, i.e. commands that require user input (for example, "pause".)

The backup process will run concurrently with your commands if you uncheck the **Do not perform operations until the commands execution is complete** box, which is checked by default.

5.3.4 Database support

Database servers, such as MS SQL Server and MS Exchange, can be problematic to backup, partially due to open files and indexes and partially due to rapid data changes. Therefore it is usually recommended that the database be suspended just before the backup (data capture). You can suspend the database and clear all caches to ensure that all transactions are completed at the moment of data capture. If it become necessary to restore a damaged database, it will be restored completely and be ready to access after recovery.

1. Volume Shadow Copy Service

Microsoft Volume Shadow Copy Service (VSS) provides the infrastructure for backup on running systems by keeping up coordination between user applications that update data on disk and backup applications. VSS is available in Microsoft Windows XP and Microsoft Windows Server 2003 operating systems.

If your database is compatible with Microsoft Volume Shadow Copy Service (VSS), then checking the **Enable VSS support** box in **Database support** window will ensure completion of all transactions before the backup process starts. The examples of VSS-aware databases are Exchange, Oracle, SQL Server.

2. Before/after data capture commands

However, VSS is not available in server operation systems older than Windows 2003 Server, and not all databases support VSS. In these cases, the transactions completion can be ensured by executing batch files or scripts that pause the appropriate Windows services and automatically resume them after data capture.

An example of a batch file, suspending the Windows services for MS Exchange:

```
net stop msxchangesa /y /y
net stop "Microsoft Exchange Routing Engine"
```

An example of a batch file, resuming the Windows services for MS Exchange:

```
net start "Microsoft Exchange System Attendant"
net start "Microsoft Exchange Event"
net start "Microsoft Exchange IMAP4"
```

```
net start "Microsoft Exchange MTA Stacks"  
net start "Microsoft Exchange POP3"  
net start "Microsoft Exchange Routing Engine"
```

Create batch files in any text editor (for example, name it *pause_services.bat* and *resume_services.bat*). Use **Edit** buttons to the right of **Before data capture command** and **After data capture command** fields, to open the **Edit Command** window where you can browse folders to find the respective batch files or scripts. A single command can be specified in the same window along with its arguments and working directory.

It is critical to note that these commands, as opposed to **Pre/post commands** above, will be executed before and after the *data capture* process, which takes seconds, while the entire backup procedure may take much longer, depending on the amount of data to be imaged. Therefore, the database idle time will be minimal.

Before/after data capture commands can also be used for other purposes, especially if VSS support is enabled. You may want to suspend an application other than a database, for example. The commands execution and the VSS actions will be sequenced as follows:

```
"before" commands -> VSS Suspend -> data capture -> VSS Resume -> "after"  
commands.
```

The backup process will run concurrently with your commands if you uncheck the **Do not perform operations until the commands execution is complete** box, which is checked by default.

3. Multi-volume snapshot

The preset is **disabled**.

Enable the **Multi-volume snapshot** feature if you are going to back up data located on multiple volumes and you must preserve its consistency (such as a database spanned across the volumes). In this case, a single snapshot for all volumes is created, which will be used for backup creation. When disabled, snapshots for volumes will be taken one by one.

5.3.5 Compression level

The preset is **Normal**.

The data will be copied without any compression, which may significantly increase the backup file size, if you select **None** as the compression level. However, if you select **Maximum** compression, the backup will take longer to create.

The optimal data compression level depends on the type of files stored in the archive. For example, even maximum compression will not significantly reduce the archive size if the archive contains essentially compressed files, such as .jpg, .pdf or .mp3. However, formats such as .doc or .xls will compress more than other file types.

Generally, it is recommended that you use the default **Normal** compression level. You might want to select **Maximum** compression for removable media to reduce the number of blank disks required.

5.3.6 Backup performance

The three options below might have a more or less noticeable effect on the backup process speed. This depends on overall system configuration and physical characteristics of devices.

1. Backup process priority

The preset is **Low**.

The priority of any process running in a system determines the amount of CPU usage and system resources allocated to that process. Decreasing the backup priority will free more resources for other CPU tasks. Increasing the backup priority may speed up the backup process due to taking resources from the other currently running processes. The effect will depend on total CPU usage and other factors.


2. HDD writing speed

The preset is **Maximum**.

Backing up in the background to an internal hard disk (for example, to the Acronis Secure Zone) may slow other programs' performance because of the large amounts of data transferred to the disk. You can limit the hard disk usage by Acronis True Image Echo Server to the desired level. To set the desired HDD writing speed for data being backed up, drag the slider or enter the writing speed in kilobytes per second.

3. Network connection speed

The preset is **Maximum**.



If you frequently backup data to network drives, think of limiting the network usage used by Acronis True Image Echo Server. To set the desired data transfer speed, drag the slider or enter the bandwidth limit for transferring backup data in kilobytes per second. This setting is also applied to an FTP connection, if an FTP server is selected as backup destination device.

5.3.7 Fast incremental/differential backup

The preset is **Use fast incremental/differential backup**.

Incremental/differential backup captures only changes in data occurred since the last backup. To speed up the backup process, Acronis True Image Echo Server determines whether the file has changed by file size and the date/time when the file was last saved. Disabling this feature will make the program compare the entire file contents to that stored in the archive.

This option relates only to disk/partition (image) backup.

5.3.8 Archive splitting

Sizeable backups can be split into several files that together make the original backup. A backup file can be split for burning to removable media or saving on an FTP server (data recovery directly from an FTP server requires the archive to be split into files no more than 2GB in size).

The preset is **Automatic**. With this setting, Acronis True Image Echo Server will act as follows:

When backing up to the hard disk: The program will create a single archive file if the selected disk has enough space and its file system allows the estimated file size.

The program will automatically split the backup into several files if the storage disk has enough space, but its file system does not allow the estimated file size.



FAT16 and FAT32 file systems have a 4GB file size limit. However, the existing hard drive's capacity can reach as much as 2TB. Therefore, an archive file might easily exceed this limit if you are going to back up the entire disk.

If you do not have enough space to store the backup on your hard disk, the program will warn you and wait for your decision as to how you plan to fix the problem. You can try to free some additional space and continue or click **Back** and select another disk.

When backing up to a diskette, CD-R/RW or DVD±R/RW: Acronis True Image Echo Server will ask you to insert a new disk when the previous one is full.

Alternatively, you can select **Fixed size** and enter the desired file size or select it from the drop-down list. The backup will then be split into multiple files of the specified size. That comes in handy when backing up to a hard disk with a view to burning the archive to CD-R/RW or DVD±R/RW later on.



Creating a backup directly on CD-R/RW or DVD±R/RW generally will take considerably more time than it would on a hard disk.

5.3.9 File-level security settings

Preserve files' security settings in archives

By default, files and folders are saved in the archive with their original Windows security settings (i.e. permissions for read, write, execute and so on for each user or user group, set in file **Properties -> Security**). If you restore a secured file/folder on a computer without the user account, specified in the permissions, you may not be able to read or modify this file.

You can disable preserving the files' security settings in archives to completely eliminate this kind of problem. Then the restored files/folders will always inherit the permissions from the folder to which they are restored (parent folder or disk, if restored to the root).

Alternatively, you can disable files' security settings during restoration, even if they are available in the archive (see *6.4.5 File-level security settings* below). The result will be the same - the files will inherit the permissions from the parent folder.

In archives, store encrypted files in decrypted state

The preset is **disabled**.

Simply ignore this option if you do not use the encryption feature available in Windows 2003 Server and Windows XP operating systems. (Files/folders encryption is set in

Properties -> General -> Advanced Attributes -> Encrypt contents to secure data).

Check the option if there are encrypted files in the backup and you want them to be accessed by any user after restore. Otherwise, only the user who encrypted the files/folders will be able to read them. Decryption may also be useful if you are going to restore encrypted files on another computer.

These options relate only to file/folders backup.

5.3.10 Media components

The preset is **disabled**.

When backing up to removable media, you can make this media bootable by writing to it additional components. As a result, you will not need a separate rescue disk.

Choose the basic components necessary for boot and restoring data on the **General** tab.

The **Acronis One-Click Restore** is a minimal addition to the image archive, stored on removable media, allowing one-click disk recovery from this archive. This means that at boot from the media and clicking "restore" all the data contained in the image will be silently restored.



Because the one-click approach does not presume user selections, such as selecting partitions to restore, Acronis One-Click Restore always restores the entire disk. Therefore, if your disk consists of several partitions and you are planning to use Acronis One-Click Restore, all the partitions must be included in the image. Any partitions missing from the image will be lost.

If you want more functionality during restoration, write a standalone version of **Acronis True Image Echo Server** to the rescue disk. Then you will be able to configure the restore task using Restore Data Wizard, use Acronis Active Restore or Acronis Universal Restore.

The **Advanced** tab lets you select full, safe or both Acronis True Image Echo Server loader versions. The safe version does not have USB, PC card or SCSI drivers and is useful only in cases where the full version does not load. If you want the computer, booted from the media to be accessible for remote control with Acronis True Image Management Console, add **Acronis Bootable Agent** to the media. If you have other Acronis products, such as Acronis Disk Director Suite, installed on your computer, the bootable versions of these programs' components will be offered as **Advanced** as well.

5.3.11 Error handling

1. Ignore bad sectors

The preset is **disabled**.

With the default setting, the program will display a pop-up window each time it comes across a bad sector and ask for user decision whether to continue or stop the backup procedure. In order to back up the valid information on a rapidly dying disk, enable ignoring bad sectors. The rest of the data will be backed up and you will be able to mount the image and extract valid files to another disk.

2. Do not show messages and dialogs while processing ("silent" mode)

The preset is **disabled**.

Corporate administrators need an option to continue a back up despite any errors that might occur without the system popping up an error box. Details of the operation, including errors, if any, could be found in the operation log.

With the silent mode enabled, the program will not display interactive windows. Instead, it will automatically handle situations requiring user intervention such as running out disk space (except for handling bad sectors, which is defined as a separate option.) No prompts will be displayed, including those for removable media or overwriting data on a tape. If an operation cannot continue without user action, it will fail.

Therefore, enable this feature if you do not want unattended backup operations hang on pop-ups and errors.

3. If an error occurs, re-attempt in (minutes)

The preset is **enabled**.

When the backup destination location on the network is not available or not reachable, the program will attempt to reach the location at the specified time interval.

5.3.12 Dual destination backup

The preset is **disabled**.

If enabled, the program will automatically place a copy of each backup being created locally to a separate location on a local drive or network share. The consistency of the additional archive copy is maintained automatically. After a backup is saved to the main location, the program compares the updated archive contents to the copy contents, and if some backups are missing from the copy, they will be copied to the external location along with the new backup.

In addition to enhancing the archive security provided with replication, this feature allows traveling users to keep a consistent copy of the laptop data both on the laptop and the corporate server. When the remote destination for the creation of the archive copy is not available, e.g. due to the network absence, the program will back up data to the local destination alone. When connected again, all changes made to the archive will be transferred to the copy during the first backup operation.

The feature provides quick desktop backup to the internal drive as an intermediate step before saving the ready backup on the network. This comes in handy in cases of slow or busy networks and time-consuming backup procedures. Disconnection during the copy transfer will not affect the backup procedure as opposed to backing up directly to the remote location.



If saving a backup copy to Acronis Secure Zone please note: even when a password is set for the Acronis Secure Zone, the copy archive will not be protected with the password.

5.3.13 Additional settings

1. Validate backup archive upon operation completion

The preset is **disabled**.

The program will check integrity of the just created or supplemented archive immediately after backup when enabled.



To check archive data integrity, you must have all incremental and differential backups belonging to the archive and the initial full backup. If any of successive backups is missing, validation is not possible.

2. Overwrite data on a tape without user confirmation

The preset is **enabled**.

When pulling a tape from the Imported media pool, Acronis True Image Echo Server will warn that you are about to lose data on the tape. To disable this warning, check the middle box.

3. Ask for first media while creating backup archives on removable media

The preset is **enabled**.

You can choose whether to display the **Insert First Media** prompt when backing up to removable media. With the default setting, backing up to removable media may be not possible if the user is away, because the program will wait for someone to press **OK** in the prompt box. Therefore, you should disable the prompt when scheduling a backup to removable media. Then, if the removable media is available (for example, CD-R/RW inserted), the task can run unattended.

4. Reset archive bit

The preset is **disabled**. The option relates only to file-level backup.

In Windows operating systems, each file has an attribute **File is ready for archiving**, available at selecting file -> **Properties** -> **General** -> **Advanced** -> **Archive and Index attributes**. This attribute, also known as archive bit, is set by the operating system each time the file is changed and can be reset by backup applications each time they include the file in a backup copy. Archive bit value is used by various applications such as databases.

With **Reset archive bit** enabled, Acronis True Image Echo Server will reset archive bits of all files being backed up. Acronis True Image Echo Server itself does not use the archive bit value. When performing incremental or differential backup, it determines whether a file has changed by the file size and the date/time when the file was last saved.

Chapter 6. Restoring the backup data

6.1 Considerations before recovery

6.1.1 Restore under Windows or boot from CD?

As mentioned above (see 2.4 *Running Acronis True Image Echo Server*), Acronis True Image Echo Server can be run in several ways. We recommend that you first try to restore data running Acronis True Image Echo Server under Windows because this method provides more functionality. Boot from the bootable media or use the Startup Recovery Manager (see 3.4 *Acronis Startup Recovery Manager*) only if Windows does not load.

The boot CD from which you loaded the program does not keep you from using other CDs with backups. Acronis True Image Echo Server is loaded entirely into RAM, so you can remove the bootable CD to insert the archive disk.



Be careful! Disk letters in standalone Acronis True Image Echo Server might sometimes differ from the way Windows identifies drives. For example, the D: drive identified in the standalone Acronis True Image Echo Server might correspond to the E: drive in Windows.




If a backup image is located on bootable media, you might have a choice of using Acronis One-Click Restore. This operation always restores the entire physical disk. Therefore, if your disk consists of several partitions, the partitions that are missing from the image will be lost. Please make sure that the image contains all disk partitions or you do not need the partitions that are not imaged before using Acronis One-Click Restore. For more information on Acronis One-Click Restore, see 5.3.10 *Media components*.

6.1.2 Network settings in rescue mode

When booted from removable media, RIS server or by Startup Recovery Manager, Acronis True Image Echo Server may not detect the network. This can occur if there is no DHCP server in your network or if your computer address was not identified automatically for some reason.

To enable a network connection, specify network settings manually in the window available at **Tools -> Options -> Network adapters**.



6.1.3 Recovering dynamic volumes

Dynamic volumes are volumes located on dynamic disks, i.e. disks managed by Windows Logical Disk Manager (LDM). For more information on dynamic disks, please refer to your Windows documentation.

Acronis True Image Echo Server can back up and recover dynamic volumes.

A dynamic volume can be recovered over the same volume or unallocated space of a dynamic group. If recovered over another volume, the target volume's contents will be overwritten with the image contents, but the type or other properties of the target volume will not be changed.

To restore a dynamic volume exactly as it is, prepare a target dynamic group without volumes. In case you want to restore a dynamic volume in place of some volumes already existing on the target disks, delete the original volumes using third-party tools, such as the Windows Disk Management tool.

Dynamic volume contents alone can be recovered onto a basic or dynamic volume without changing the target volume type. Acronis True Image Echo Server has the **Create dynamic volume** tool so that you would be able to prepare the desired volumes on the target disk.

Backward conversion of dynamic volume to basic disks can be performed, if need be, using the **Add new disk** operation (see *Chapter 14. Adding a new hard disk*).

With these tools, anywhere-to-anywhere data recovery becomes available, in terms of basic disks and dynamic volumes of any type (simple, spanned, striped, mirrored or RAID 5). The tools are available in bootable program version. Having booted the Acronis environment, you can easily prepare the desired dynamic group on bare metal or a computer with non-Windows operating system.

For how to use the above tools see *6.5 Creating dynamic disks and volumes*.


6.2 Restoring files and folders from file archives

Here we describe how to restore files/folders from a file backup archive. You can restore the desired files/folders from a disk/partition image as well. To do so, mount the image (see *10.2.2 Mounting an image*) or start the image restoration and select **Restore specified files or folders** (see *6.3 Restoring disks/partitions or files from images*).



To restore files and folders from an XFS, JFS, or ReiserFS image, mount it under Linux and copy the necessary files and folders.

1. Start the **Restore Data Wizard** by clicking on the restore operation icon in the main program window.
2. Select the archive. If the archive is located in Acronis Secure Zone, select it to choose the archive on the next step.



If the archive is located on removable media, e.g. CD, first insert the last CD and then insert disks in reverse order when Restore Data Wizard prompts.



Data recovery directly from an FTP server requires the archive to consist of files no more than 2GB in size. If you suspect that some of the files may be larger, first copy the entire archive (along with the initial full backup) to a local hard disk or network share disk. See notes and recommendations for supporting FTP server in *1.3.2 Supported storage media*.


If you added a comment to the archive, it will be displayed to the right of the drives tree. If the archive was protected with a password, Acronis True Image Echo Server will ask for it. The comment and the **Next** button will be unavailable until you enter the correct password.

3. If the selected archive contains incremental backups, Acronis True Image Echo Server will suggest that you select one of successive incremental backups by its creation date/time. Thus, you can return the files/folders to a specific time and date.




To restore data from an incremental backup, you must have all previous incremental backups and the initial full backup. If any of successive backups is missing, restoration is not possible.

To restore data from a differential backup, you must have the initial full backup as well.



4. Select a folder on your computer where you want to restore selected folders/files (a target folder). You can restore data to their original location or choose another folder, if necessary.

5. Select files and folders to restore. You can choose to restore all data or browse the archive contents and select the desired folders or files.




6. Select the options for the restoration process (that is, pre/post restoration commands, restoration process priority, file-level security settings etc.). You may **Use default options** or **Set the options manually**. If you set options manually, the settings will be applied only to the current restore task. Alternatively, you can edit the default options from the current screen. Then your settings will be saved as default. See *6.4 Setting restore options* for more information.

7. Set filters for the specific types of files that are not to be restored. For example, you may want hidden and system files and folders, as well as files with **.~**, **.tmp** and **.bak** extensions, not to be restored from the archive.

You can also apply custom filters, using the common Windows masking rules. For example, to exclude all files with extension **.exe**, add ***.exe**. **My???.exe** will reject all **.exe** files with names consisting of five symbols and starting with "my".

All of these settings will take effect for the current task. How to set the default filters that will be called each time you restore data, see *6.4.1 Files to exclude from restoration*.

8. The next selection allows you to keep useful data changes made since the selected backup was created. Choose what to do if the program finds in the target folder a file with the same name as in the archive.



- **Overwrite existing file** – this will give the archived file unconditional priority over the file on the hard disk.
- **Overwrite existing file if it is older** – this will give the priority to the most recent file modification, whether it be in the archive or on the disk
- **Do not overwrite existing file** – this will give the file on the hard disk unconditional priority over the archived file.

9. At the final step, the restoration summary is displayed. Up to this point, you can click **Back** to make changes in the created task. Clicking **Proceed** will launch the task.

10. The task progress will be shown in a special window. You can stop the procedure by clicking **Cancel**. Please keep in mind that the aborted procedure still may cause changes in the destination folder.

6.3 Restoring disks/partitions or files from images


To restore a partition (disk) from an image, Acronis True Image Echo Server must obtain **exclusive access** to the target partition (disk). This means no other applications can access it at that time. If you receive a message stating that the partition (disk) can not be blocked, close applications that use this partition (disk) and start over. If you can not determine which applications use the partition (disk), close them all.

6.3.1 Starting the Restore Data Wizard

Start the **Restore Data Wizard** by clicking on the restore operation icon in the main program window.

6.3.2 Archive selection

1. Select the archive. If the archive is located in Acronis Secure Zone, select it to choose the archive at the next step.



If the archive is located on removable media, e.g. CD, first insert the last CD and then insert disks in reverse order when Restore Data Wizard prompts.



Data recovery directly from an FTP server requires the archive to be split into files no more than 2GB in size. If you suspect that some of the files may be larger, first copy the entire archive (along with the initial full backup) to a local hard disk or network share disk. See notes and recommendations for supporting FTP server in *1.3.2 Supported storage media*.

If you added a comment to the archive, it will be displayed to the right of the drives tree. If the archive was protected with a password, Acronis True Image Echo Server will ask for it. The partitions layout, the comment and the **Next** button will be unavailable until you enter the correct password.

2. If the selected archive contains incremental backups, Acronis True Image Echo Server will suggest that you select one of successive incremental backups by its creation date/time. Thus, you can return the disk data to a certain moment.




To restore data from an incremental backup, you must have all previous incremental backups and the initial full backup. If any of successive backups is missing, restoration is not possible.

To restore data from a differential backup, you must have the initial full backup as well.

6.3.3 Restoration type selection

Select what you want to restore:



Restore specified files or folders

With this selection, you will be further offered to select where to restore selected folders/files (original or new location), choose files/folders to be restored and so on. These steps look like those in file archive restore. However, watch your selection; if you want to restore files instead of disk/partition, uncheck the unnecessary folders. Otherwise you will restore a lot of extra files. Then you will be taken directly to Restoration Summary screen (*6.3.14 Restoration summary and executing restoration*)

Restore disks or partitions

Having selected a usual way of disks/partitions recovery, you will have to make all settings described below.

Using Active Restore

When restoring a system disk/partition image (except for Windows Vista images) from Acronis Secure Zone, you will have the third choice – to use **Acronis Active Restore**. Having selected this option, you will proceed directly to the summary window (*6.3.14 Restoration summary and executing restoration*). A few seconds after pressing **Proceed**, the computer will reboot to the restored system. Log in and start work – no more reboots or other actions are required. For more about Acronis Active Restore, see *3.5 Acronis Active Restore*.




When performing Active Restore, the Acronis True Image Echo Server always restores the entire system disk. Therefore, if your disk consists of several partitions, the partitions which are missing from the image will be lost. Please make sure that the image contains all disk partitions or you do not need the partitions that are not imaged before using Acronis Active Restore.

However, you can choose an ordinary way of restoration for that image. This will allow you to make changes to the restored partition that would not be possible when using Acronis Active Restore.

Finally, if you are not going to recover the system, but only want to repair damaged files, select **Restore specified files or folders**.

6.3.4 Selecting a disk/partition to restore

The selected backup can contain images of several partitions or even disks. Select which disk/partition to restore.



Disks and partitions images contain a copy of track 0 along with the MBR (Master Boot Record). It appears in this window in a separate line. You can choose whether to restore MBR and track 0 by checking the respective box. Restore the MBR if it is critical to your system boot.

6.3.5 Restoring NT disk signature

Windows NT disk signature is a record in MBR that keeps information about all the partitions on any disk ever connected to the computer under that operating system.

When restoring MBR along with a disk backup, choose what the program must do with a disk signature:

Create new

The program will generate a new disk signature for the recovered drive.

Set this option when you are restoring an image backup on another hard drive (i.e. cloning the volume, not recovering the corrupted one). If the option is not set, the cloned disk will not be able to boot independently without the source drive after the cloning process is complete. This happens because during Windows startup the loader checks disk signatures of all connected drives. If two identical disk signatures are found, the loader changes the signature of the cloned drive. But the loader cannot modify the cloned drive's registry. The *MountedDevices* registry values of the cloned drive store the disk signature of the original drive. Thus, the cloned disk will not be available if the original disk is disconnected.

Recover from backup

The program will replace the existing disk signature with the one from the backup.

Set this option when you are performing a disaster recovery restoration. Recovering a disk signature will allow you to:

- access all Windows Restore Points on the recovered disk,
- access VSS snapshots via Windows Vista's "Previous Versions" feature on the recovered disk,
- keep licensing and other information for installed applications as some programs may use NT disk signature for licensing and other purposes,
- keep the existing scheduled task without the need to re-create or edit it, as all scheduled tasks of the program use the NT disk signature for disk identification.

6.3.6 Selecting a target disk/partition

1. Select a target disk or partition where you want to deploy the selected image. You can restore data to its initial location, to another disk/partition or to an unallocated space. The target partition should be at least the same size as the uncompressed image data.




All the data stored on the target partition will be replaced by the image data, so be careful and watch for non-backed-up data that you might need.

When restoring a Windows system disk and select a target disk, the program compares critical for the system start devices, found in the image registry and the target computer registry.

If the chipset, motherboard or mass storage device are different, there is a risk that the system will not be able to boot. Then you will be prompted whether you want to buy **Acronis Universal Restore**. To find out more about this option, see *3.6 Acronis Universal Restore*. To buy the option, follow the link.

If you already have Acronis Universal Restore, the prompt will not come up and you will have an option to enable Acronis Universal Restore later in the Restore Data Wizard.

2. When restoring an entire disk, the program will analyze the target disk structure to see if the disk is free.



If there are partitions on the target disk, you will be prompted by the **Nonempty Destination Hard Disk Drive** window stating that the destination disk contains partitions, perhaps with data.

You will have to select between:

- **Yes, I want to delete all the partitions on the destination hard disk before restoring** – all existing partitions will be deleted and all their data will be lost.
- **No, I do not want to delete partitions** – no existing partition will be deleted, discontinuing the recovery operation. You will be able to cancel the operation or return to select another disk.



Note that no real changes or data destruction will be performed at this time! For now, the program will just map out the procedure. All changes will be implemented only when you click **Proceed** in the wizard's final window.

To continue, select the first choice and click **Next**. You will be taken directly to step *6.3.11 Restoring several disks or partitions at once*.

6.3.7 Changing the restored partition type

When restoring a partition, you can change its type, though it is not required in most cases.

To illustrate why you might need to do this, let's imagine that both the operating system and data were stored on the same primary partition on a damaged disk.

If you are restoring a system partition to the new (or the same) disk and want to load an operating system from it, you will select **Active**.

If you restore a system partition to another hard disk with its own partitions and OS, most likely you will need only the data. In this case, you can restore the partition as **Logical** to access the data only.

By default, the original partition type is selected.



Selecting **Active** for a partition without an installed operating system could prevent your server from booting.

6.3.8 Changing the restored partition file system

You can change the partition file system during its restoration, although it is seldom required. Acronis True Image Echo Server can make the following file system conversions: **FAT 16 -> FAT 32** and **Ext2 -> Ext3**. For partitions with other native file systems, this option is not available.




Let us imagine you are to restore a partition from an old, low-capacity FAT16 disk to a newer disk. FAT16 would not be effective and might even be impossible to set on the high-capacity hard disk. That's because FAT16 supports partitions up to 4GB, so you will not be able to restore a 4GB FAT16 partition to a partition that exceeds that limit without changing the file system. It would make sense here to change the file system from FAT16 to FAT32.

However, keep in mind that not all operating systems support FAT32. MS-DOS, Windows 95 and Windows NT 3.x, 4.x do not support FAT32 and will not be operable after you restore a partition and change its file system. These can be normally restored on a FAT16 partition only.

6.3.9 Changing the restored partition size and location

You can resize and relocate a partition by dragging it or its borders with a mouse or by entering corresponding values in the appropriate fields.

Using this feature, you can redistribute the disk space between partitions being restored. In this case, you will have to restore the partition to be reduced first.



These changes might be useful if you are to copy your hard disk to a new, high-capacity one by creating its image and restoring it to a new disk with larger partitions.

6.3.10 Assigning a letter to the restored partition

Acronis True Image Echo Server will assign an unused letter to a restored partition. You can select the desired letter from a drop-down list. If you set the switch to **No**, no letters will be assigned to the restored partition, hiding it from OS.

You should not assign letters to partitions inaccessible to Windows, such as to those other than FAT and NTFS.

6.3.11 Restoring several disks or partitions at once


During a single session, you can restore several partitions or disks, one by one, by selecting one disk and setting its parameters first and then repeating these actions for every partition or disk to be restored.

If you want to restore another disk (partition), select **Yes, I want to restore another partition or hard disk drive**. Then you will return to the partition selection window (7.3.4) again and will have to repeat the above steps. Otherwise, do not set this switch.

6.3.12 Using Acronis Universal Restore

Acronis Universal Restore is an add-on to Acronis True Image Echo Server. It is purchased separately and installed from a separate setup file. The following is true for Acronis True Image Echo Server installations including Acronis Universal Restore.

1. Using Acronis Universal Restore will help you create a bootable system clone on different hardware (for more information see *3.6 Acronis Universal Restore*). Choose this when restoring a system disk to a computer with a dissimilar processor, different motherboard or other mass storage device than in the imaged system.



2. If the target hardware has a specific mass storage controller (such as a SCSI, RAID, or Fibre Channel adapter) for the hard disk, you can install the appropriate driver manually, bypassing the automatic driver search-and-install procedure.

Use this option only if the automatic search-and-install procedure was unsuccessful.

Acronis Universal Restore uses three sources for drivers:

- the driver repository - a folder or folders on a network drive or CD specified in restore options. If you have not specified the driver repository in advance, you can do it at next step.
- the mass storage device driver specified by the user at the current step
- the Windows default driver storage folders (in the image being restored).

The program will find the most suitable drivers of all available drivers and install them into the restored system. However, the driver defined by the user, will have the priority. It will be installed, with appropriate warnings, even if the program finds the better driver.



When restoring the system to a virtual machine that uses SCSI hard drive controller, be sure to specify SCSI drivers for virtual environment in the **Specifying Mass Storage Drivers** window. Use drivers bundled with your virtual machine software or download the latest drivers versions from the software manufacturer website.

6.3.13 Setting restore options

Select the options for the restoration process (that is, pre/post restoration commands, restoration process priority etc.). You may **Use default options** or **Set the options manually**. If you set the options manually, the settings will be applied only to the current restore task. Alternatively, you can edit the default options from the current screen. Then your settings will be saved as default. See *6.4 Setting restore options* for more information.

6.3.14 Restoration summary and executing restoration

1. At the final step, the restoration summary is displayed. Up to this point, you can click **Back** to make changes in the created task. If you click **Cancel**, no changes will be made to disk(s). Clicking **Proceed** will launch the task execution.

2. The task progress will be shown in a special window.


You can stop the procedure by clicking **Cancel**. However, it is critical to note that the target partition will be deleted and its space unallocated – the same result you will get if the restoration is unsuccessful. To recover the “lost” partition, you will have to restore it from the image again.

If Acronis Universal Restore finds no Hardware Abstraction Layer (HAL) or mass storage devices drivers compatible with the new hardware in all available sources, you will be prompted to browse to a network share drive or insert a floppy disk or CD with the necessary drivers. Upon starting Windows, it will initialize the standard procedure for installing new hardware. At this point, you will be able to specify drivers for devices if Windows cannot find them automatically.

6.4 Setting restore options

To view or edit the default restore options, select **Tools -> Options -> Default Restoration Options** from the main program menu.

You can edit the default (or set the temporary) restore options while creating a restore task as well.



6.4.1 Files to exclude from restoration

The preset is **Restore all files**.

You can set the default filters for the specific types of files that are not to be restored. Use the common Windows masking rules. For example, to exclude all files with extension .exe, add ***.exe**. **My???.exe** will exclude all .exe files with names, consisting of five symbols and starting with "my".

This option is effective only when restoring files from file/folders archives. When restoring files from a disk/partition image, you cannot filter out any files.

6.4.2 Files overwriting mode

This option allows you to keep useful data changes made since the backup being restored was done. Choose what to do if the program finds in the target folder a file with the same name as in the archive.

Overwrite existing file – this will give the archived file unconditional priority over the file on the hard disk.

Overwrite existing file if it is older – this will give the priority to the most recent file modification, whether it be in the archive or on the disk.

Do not overwrite existing file – this will give the file on the hard disk unconditional priority over the archived file.

This option is effective only when restoring files from file/folders archives.

6.4.3 Pre/post commands

You can specify commands or batch files to be automatically executed before and after the restore procedure. Click **Edit** to open the **Edit Command** window where you can easily input the command, its arguments and working directory or browse folders to find a batch file.

The program does not support interactive commands, i.e. commands that require user input (for example, "pause".)

The backup process will run concurrently with your commands if you uncheck the **Do not perform operations until the commands execution is complete** box, which is checked by default.

6.4.4 Restoration priority

The default setting – **Low**.

The priority of any process running in a system determines the amount of CPU usage and system resources allocated to that process. Decreasing the restoration priority will free more resources for other CPU tasks. Increasing of restoration priority may speed up the restore process due to taking resources from the other currently running processes. The effect will depend on total CPU usage and other factors.

6.4.5 File-level security settings

The preset is **Restore files with their security settings**.

If the files' security settings were preserved during backup (see *5.3.9 File-level security settings*), you can choose whether to restore files' security settings or let the files inherit the security settings of the folder where they will be restored.


This option is effective only when restoring files from file/folders archives.

6.4.6 Specifying mass storage drivers

This option appears only in those computers' options, where Acronis Universal Restore is installed.



Acronis Universal Restore is an option to Acronis True Image Echo Server. It should be purchased separately and installed from a separate setup file. For more information see [3.6 Acronis Universal Restore](#).



Here you can specify a path to the driver repository on a network drive or CD where Acronis Universal Restore will search for drivers at restoring a system disk on dissimilar hardware. If several paths are specified, the program will scan all locations and choose the most suitable driver.

6.4.7 Additional settings

1. Set current date and time for the restored files

The preset is **enabled**.

Choose whether to restore files' date and time from the archive or assign the files the current date and time.

2. Before data is restored from the archive, Acronis True Image Echo Server can check its integrity. If you suspect that the archive might have been corrupted, select **Validate backup archive before restoration**.



To check archive data integrity you must have all incremental and differential backups belonging to the archive and the initial full backup. If any of successive backups is missing, validation is not possible.

3. Having restored a disk/partition from an image, Acronis True Image Echo Server can check the integrity of the file system. To do so, select **Check file system after restoration**.



Verification of the file system is available only when restoring disk/partitions under Windows and for FAT16/32 and NTFS file systems.

4. Restore file and folders without full path

The preset is **disabled**.

When enabled, files and folders are restored directly to the folder that you specified as a target folder. When disabled, the full path to the files and folders that exists in the backup will be reproduced within the target folder.

5. Change SID after restoration is finished

The preset is **disabled**.

Acronis True Image Echo Server can generate a unique security identifier (SID) for the restored system. You do not need a new SID when restoring a system on the same computer where the image was taken from or when creating a full duplicate that will replace the original system. Generate a new SID if the original and the restored systems will work concurrently in the same workgroup or domain.

6. Restart the machine automatically

The preset is **disabled**.

Sometimes one or more reboots may be required during the restoration process. With this option enabled, the program will not ask you for permission to reboot now or later, but immediately reboots the machine.

7. Use FTP in active mode

The preset is **disabled**.

Previous versions of the software required usage of passive mode for the target FTP server and usage of TCP and UDP ports 20 and 21 on the source computer. The current version has no such limitations: you can use either active or passive mode.

Check this option if the FTP server where the target backup is stored uses active mode and specify the port number in the **FTP port number** field.

It is recommended that you change the source computer firewall settings to disable the **Routing and Remote Access** Windows service.

6.4.8 Error handling

1. Do not show messages and dialogs while processing ("silent" mode)

The preset is **disabled**.

With the silent mode enabled, the program will not display interactive windows. Instead, it will automatically handle situations requiring user intervention. No prompts will be displayed, including those for inserting removable media or the next tape. If an operation cannot continue without user action, it will fail. Details of the operation, including errors, if any, could be found in the operation log.

2. If an error occurs, re-attempt in (minutes)

The preset is **enabled**.

When the backup location on the network is not available or not reachable, the program will attempt to reach the location at the specified time interval.

6.5 Creating dynamic disks and volumes

Acronis True Image Echo Server must obtain **exclusive access** to the disks to perform operations with disks and volumes. This means no other applications can access it at that

time. Please close all other applications that use the disks (such as Windows Disk Management) before starting the dynamic volume creation wizard.

6.5.1 Creating dynamic volumes

Acronis True Image Echo Server can perform this operation in standalone (rescue) mode as well as under Windows control. Having booted to the Acronis environment, you can easily prepare the desired dynamic group on bare metal or a computer with a non-Windows operating system.

The operation supports both dynamic disks and MBR or GPT basic disks. Basic disks will be converted to dynamic.




All data contained on the basic disk and the basic disk partitioning will be lost. On dynamic disks, only unallocated space will be used for the new volume.

An MBR basic disk must have at least 1MB of free space at the end of the disk for the dynamic disk database.

To create a dynamic volume:

1. Close all applications that use the disk(s) on which the volume is to be created.
2. Start the Dynamic Volume Creation Wizard by selecting **Tools -> Create Dynamic Volume** in the main program menu.
3. Select basic, dynamic or newly connected disks on which the dynamic volume will be created. Dynamic disks are selected by default. You can deselect any, if need be, later in the wizard.

If you tick off disks other than dynamic, these will be converted to dynamic disks and included in the dynamic group. However, this will be done when the operation starts. While you are using the wizard, no changes are made to disks.




4. Select the type of dynamic volume that will be created: simple/spanned, striped, mirrored or RAID 5.
5. Specify amount of space that the dynamic volume will occupy on each of the selected disks. The value you set is adjusted to the selected volume type.

For a spanned volume, amount of space on each disk is selected independently. If only one disk is selected, a simple volume is created.

Striped, mirrored and RAID 5 volumes imply even distribution of data between disks. Therefore, the volume must occupy the same space on each disk. If you set different values, your latest setting will be applied to all the disks. If the set value is more than unallocated space on any disk, the minimal available space amount will be applied to all the disks. The resulting volume size is displayed under the disk selection field.

At this step, you can deselect disks that you do not want to be included in the volume.




6. Click **Proceed** in the summary window.

On completion of operations, the dynamic volumes are unformatted and have no letters assigned. You will be able to assign the letters using Windows Disk Management tool after restoring Windows on the created volumes.

Chapter 7. Scheduling tasks

Acronis True Image Echo Server allows you to schedule periodic backup and archive validation tasks. Doing so will give you peace of mind, knowing that your data are safe.


You can create more than one independently scheduled task. For example, you can back up your current project daily and back up the application disk once a week.



All the scheduled tasks appear in the **Scheduled Tasks** window, where you can start, stop, edit, delete and rename them. To navigate to the **Scheduled Tasks** window, click **Tasks** in the **Manage Tasks** group or select the **Task Scheduling** category on the sidebar.

7.1 Creating scheduled tasks

1. To start the **Schedule Task Wizard**, click **Create** on the **Scheduled Tasks** window toolbar or select **Operations -> Schedule Task** from the main menu.
2. Choose the **Backup** or **Validate** operation. If the latter is the case, choose the archive in the next window and you will be taken straight to step 4.
3. If backup is your choice, configure a backup task in the usual way (see *Chapter 5. Creating backup archives*). If you choose to create the backup archive on a network drive, enter a user name and a password for the drive access.
4. Set the task execution periodicity.



- **Manually later** – the task will be saved, but not launched automatically. You will be able to launch it later by clicking **Run** in the **Scheduled Tasks** window
- **Daily** – the task will be executed once a day or once in several days
- **Weekly** – the task will be executed once a week or once in several weeks on the selected day
- **Monthly** – the task will be executed once a month on the selected day
- **One time only** – the task will be executed once at the specified time and day
- **Free disk space change** – the task will be executed when the free disk space changes by the specified amount
- **When my computer starts** – the task will be executed at every OS startup
- **When I log on** – the task will be executed each time the current user logs in to the OS
- **When my computer shuts down** – the task will be executed before every server shutdown or reboot
- **When I log off** – the task will be executed each time the current user logs off of the OS.



Some of these options might be disabled depending on the operating system.

5. Specify the task start time and other schedule parameters, according to the selected periodicity (see 7.1.1 - 7.1.5).
6. Next you will have to specify the name of the user who owns the executed task; otherwise no scheduled execution will be available.



In the upper field, enter a user name. Enter a password twice in two fields below.

7. At the final step, the task configuration is displayed. Up to this point, you can click **Back** to make changes in the created task. If you click **Cancel**, all settings will be lost. Click **Finish** to save the task.

8. The task schedule and default name appear in the **Scheduled Tasks** window. You can rename the task, if need be.

7.1.1 Setting up daily execution

If you select daily execution, set the **Start time** and days on which you want to execute the task:

- **Every day**
- **Weekdays**
- **Every x days** – once in several days (specify the interval).
- **Repeat task every** – set this if the task must be performed several times a day.



If the computer is off when the scheduled time comes, the task won't be performed, but you can force the missed task to launch at the next system startup by checking a box under the **Start time** fields.

7.1.2 Setting up weekly execution

If you select weekly execution, set the **Start time**, specify the task execution periodicity in the **Every x weeks** box (every week, every two weeks, etc.) and check the days on which to execute the task.




If the computer is off when the scheduled time comes, the task won't be performed, but you can force the missed task to launch at the next system startup by checking a box under the **Start time** fields.

7.1.3 Setting up monthly execution

If you select monthly execution, set the **Start time** and days on which to execute the task:


- **Day** – on the specified date
- **The <specify a day>** – on the specified day (e.g. on second Tuesday or fourth Friday); select this from the drop-down lists.



If the computer is off when the scheduled time comes, the task won't be performed, but you can force the missed task to launch at the next system startup by checking a box under the **Start time** fields.

7.1.4 Setting up one-time execution


If you select the one-time execution, set the **Start time** and date on which to execute the task:



If the computer is off when the scheduled time comes, the task won't be performed, but you can force the missed task to launch at the next system startup by checking a box under the **Start time** fields.

7.1.5 Setting up event-driven execution

Execution on increasing or decreasing free space on a disk. The task will be started when the free space on the either disk selected for the backup changes by the specified value. The preset is 20MB.



7.2 Managing scheduled tasks

The task Status, Schedule, Last Run Time and Last Result are shown in the **Scheduled Tasks** window. To view the other task details, right-click on its name.

There are two ways of changing the task parameters. Editing allows you to change any task parameters. This is performed in the same way as creation, however, the earlier selected options will be set, so you have to enter only the changes. To edit a task, select it and click **Edit** on the toolbar.

If you want to change only the task start trigger (time or event), click **Schedule** on the toolbar. Then you will have to perform only scheduling steps, leaving other settings the same.

To delete a task with confirmation, select it and click **Delete** on the toolbar.

To rename a task, select it, click **Rename** on the toolbar, enter the new task name and press Enter.

You have an option to duplicate a task so that you need program it only once. Select the task and click **Clone** on the toolbar. Pass through the same wizard as when editing a task and make changes if necessary. As opposed to editing, the result will be saved as a separate task. You will have the option to rename the clone for better identification.

Chapter 8. Managing the Acronis Secure Zone

The Acronis Secure Zone is a special partition for storing archives on the computer system itself. For more information see *3.3 Acronis Secure Zone*.

When you click **Manage Acronis Secure Zone** in the menu, the program searches for the zone on all local drives. If a zone is found, the wizard will offer to manage it (consolidate or remove backups, resize or change the password) or delete. If there is no zone, you'll be prompted to create it.

If the Acronis Secure Zone is password-protected, the proper password must be entered before any operation can take place.


8.1 Creating Acronis Secure Zone

The Acronis Secure Zone can be located on any internal disk. It is created using unallocated space, if available, or at the expense of free space on a partition. Partition resizing may require a reboot.


A computer can have only one Acronis Secure Zone. To create a zone on another disk, you must first delete an existing zone.

1. Before creating a zone, you may want to estimate its size. To do so, start a backup and select all data you are going to copy into it. At the **Set Backup Options** step, choose **Set the options manually**, then set the compression level. You will see the estimated full backup size (for disk/partition backup) or the approximate compression ratio (for file-level backup) with which you can calculate the estimated full backup size. Multiply this by about 1.5 to be able to create incremental or differential backups.


2. If there are several disks installed, select one on which to create Acronis Secure Zone.



3. Select the partitions from which space will be used to create the zone.



4. In the next window, enter the Acronis Secure Zone size or drag the slider to select any size between the minimum and maximum ones.



The minimum size is approximately 35MB, depending on the geometry of the hard disk. The maximum size is equal to the disk's unallocated space plus the total free space on all partitions selected at the previous step.

When creating the zone, the program will first use the unallocated space. If there is not enough unallocated space, the selected partitions will be decreased. Partition resizing may require a reboot.



Please keep in mind that reducing a system partition to the minimum size might prevent your operating system from booting.

5. You can set a password to restrict access to the zone. The program will ask for the password at any operation relating to it, such as data backup and recovery, mounting images or validating archives on the zone, using the Acronis Startup Recovery Manager with the F11 key, resizing and deleting the zone.



Acronis True Image Echo Server repair or update will not affect the password. However, if the program is removed and then installed again while keeping the Acronis Secure Zone on the disk, the password for the zone will be reset.

6. After this, you will be prompted to activate Acronis Startup Recovery Manager, which will enable you to start Acronis True Image Echo Server at boot time by pressing F11 key. Or, you can activate this feature later from the main program window.

7. Then you will see a list of operations to be performed on partitions (disks).

After you click **Proceed**, Acronis True Image Echo Server will start creating the zone. Progress will be reflected in a special window. If necessary, you can stop zone creation by clicking **Cancel**. However, the procedure will be canceled only after the current operation is finished.

Acronis Secure Zone creation might take several minutes or more. Please wait until the whole procedure is finished.

8.2 Resizing the Acronis Secure Zone

1. When prompted by the wizard, select **Manage Acronis Secure Zone**.

2. Select to increase or decrease the zone. You might need to increase it to provide more space for archives. The opposite situation could arise if either partition lacks free space.

3. Select partitions from which free space will be used to increase Acronis Secure Zone or that will receive free space after the zone is reduced.

4. Enter the new size of the zone or drag the slider to select the size.

When increasing the Acronis Secure Zone, the program will first use unallocated space. If there is not enough unallocated space, the selected partitions will be decreased. Resizing of the partitions may require a reboot.



Please keep in mind that reducing a system partition to the minimum size may prevent your operating system from booting.

When reducing the zone, any unallocated space, if the hard disk has it, will be allocated to the selected partitions along with the space freed from the zone. Thus, no unallocated space will remain on the disk.

5. Next you will see a list of briefly described operations to be performed on partitions (disks).

After you click **Proceed**, Acronis True Image Echo Server will start resizing the zone. Progress will be reflected in a special window. If necessary, you can stop the procedure by clicking **Cancel**. However, the procedure will be canceled only after the current operation is finished.

Zone resizing can take several minutes or longer. Please wait until the whole procedure is finished.

8.3 Changing the password for Acronis Secure Zone

1. When prompted by the wizard, select **Manage Acronis Secure Zone**.
2. Select **Change password**.




3. Enter the new password and confirm it or select **Do not use password protection**. You can also select a secret question that will be asked in case you forget the password.
4. To perform the password change operation, click **Proceed** in the final wizard window.

8.4 Managing backups in the Acronis Secure Zone

The purpose of the Acronis Secure Zone management is to manually free up space in the Acronis Secure Zone by deleting or consolidating backups.

1. Invoke the **Manage Acronis Secure Zone** Wizard (Tools -> Manage Acronis Secure Zone) and click **Next**.
2. On the Action Selection step, choose **Manage archives in Acronis Secure Zone**.
3. On the Backup Date selection step, select an action: **consolidate** or **remove**.



4. [Consolidation]: Select the backup. Backups created earlier will be consolidated into the selected backup. Backups created later will remain untouched.

[Remove]: Select the backup you want to remove. Be careful: all dependent incremental and differential backups will be also removed.

5. After you click **Proceed**, Acronis True Image Echo Server will start backup consolidation\deletion.

8.5 Deleting Acronis Secure Zone

Acronis Secure Zone deletion will destroy all backups stored in the zone.

There is an option to keep Acronis Secure Zone along with its contents (which will enable data recovery on booting from bootable media) or remove Acronis Secure Zone if you remove Acronis True Image Echo Server from the system. To delete the zone without uninstalling the program, proceed as follows.

1. When prompted by the wizard, select **Remove Acronis Secure Zone**.
2. Select the partitions to which you want to add the space freed from the zone. If you select several partitions, the space will be distributed proportionally to each partition.
3. Next, you will see a list of briefly described operations to be performed on partitions (disks).

After you click **Proceed**, Acronis True Image Echo Server will start deleting the zone. Progress will be reflected in the opened window. If necessary, you can stop the procedure by clicking **Cancel**. However, the procedure will be canceled only after the current operation is finished.

Zone deletion might take several minutes or more. Please wait until the whole procedure is finished.

Chapter 9. Creating bootable media

9.1 Creating Acronis rescue media

You can run Acronis True Image Echo Server on a bare metal or on a crashed computer that cannot boot. You can also back up disks on a non-Windows computer, copying all its data sector-by-sector into the backup archive. To do so, you will need bootable media with the standalone Acronis True Image Echo Server version.

Because Acronis True Image Echo Server is available only as a download, you must create bootable media using the Bootable Media Builder. For this, you will need a blank CD-R/RW, DVD±R/RW, several formatted diskettes (the wizard will tell you the exact number), or any other media your server can boot from, such as a Zip drive.

Acronis True Image Echo Server also has the ability to create an ISO image of a bootable disk on the hard disk. If there is a Microsoft RIS server in your local network, an IT administrator can save the bootable data on this server as well. Then any networked computer will be able to boot Acronis True Image Echo Server from the RIS package.

If you have other Acronis products, such as Acronis Disk Director Server, installed on your computer, you can include standalone versions of these programs on the same bootable disk as well.



If you have chosen not to install the Bootable Media Builder during Acronis True Image Echo Server installation, you will not be able to use this feature.

1. Click **Create Bootable Rescue Media** on the toolbar or the sidebar, or select **Create Bootable Rescue Media** from the **Tools** menu. You can also run the Bootable Rescue Media Builder without loading Acronis True Image Echo Server by selecting **Programs -> Acronis -> True Image -> Bootable Rescue Media Builder** from the **Start menu**.

2. Select which components of Acronis programs you want to place on the bootable media.

Acronis True Image Echo Server offers the following components:

- Acronis True Image Echo Server full version


Includes support of USB, PC Card and SCSI interfaces along with the storage devices connected via them, and therefore is highly recommended.

- Acronis True Image Echo Server safe version

Does not include USB, PC Card, or SCSI drivers. Recommended for use in case of problems with running Full version.

To find more about components of other Acronis products, see the respective user guides.


The **Start automatically after** parameter specifies the timeout interval for the boot menu. If this parameter is not specified, at booting a computer the program will display the boot menu and wait for someone to select whether to boot the OS or the Acronis component. If you set 10 sec, for example, the program will launch in 10 seconds after the menu is displayed.



3. Select the type of bootable media (CD-R/RW, DVD±R/RW or 3.5" diskettes) to create. If your BIOS has this feature, you can create other bootable media such as removable USB flash drives. You can also choose to create a bootable disk ISO image or save bootable data on the RIS server.



When using 3.5" diskettes, you will be able to write on a diskette (or a set of the diskettes) only one component at a time — for example, Acronis True Image Echo Server. To write another component, start the Bootable Media Builder once again.



4. If you are creating a CD, DVD, diskettes or any removable media, insert the blank disk so the program can determine its capacity. If you chose to create a bootable disk ISO image, specify the ISO file name and the folder in which to place it. If you chose to save bootable data on a RIS server, specify the server and provide the user name and password to access it.

5. Next, the program will calculate how many blank disks are required (in case you have not chosen ISO or RIS) and give you time to prepare them. When you are finished, click **Proceed**.

After you create a boot disk, mark it and keep it in a safe place.

9.2 Creating a Win PE ISO with Acronis True Image Echo Server

Windows Preinstallation Environment (Win PE) is a minimal Windows system based on the Windows XP Professional and the Windows Server 2003 kernels. Win PE is commonly used by OEMs and corporations for deployment, test, diagnostic and system repair purposes. Using Acronis True Image Echo Server in Windows Preinstallation Environment allows a combination of Acronis True Image Echo Server and Win PE facilities and provides more functionality than using only-Acronis bootable media. The Acronis Universal Restore add-on to Acronis True Image Echo Server, if installed, will also be included in the ISO image.

To add the Acronis True Image Echo Server plug-in to your Win PE distribution:

1. Make sure that **Acronis Bart PE plug-in** is installed on the computer (the default path is \Program Files\Acronis\TrueImageEchoServer\BartPE). If not, run Acronis True Image Echo Server setup file, choose **Modify** and install the Acronis Bart PE plug-in.

Acronis Win PE ISO Builder locates the Acronis Bart PE plug-in using the registry key **HKEY_LOCAL_MACHINE\SOFTWARE\Acronis\TrueImageEchoServer\Settings\BartPE**, created at the time of installation. If you moved the Bart PE plug-in to another folder after installation, change the key accordingly. If the above key is missing, the builder does not work.

2. Insert your Win PE distribution CD into the media drive of the computer. If you have a distribution copy on the hard disk, copy the path to it. The distribution files must be unpacked and allocated in a separate folder.

3. Select Programs -> Acronis ->Acronis True Image Echo Server -> Acronis Win PE ISO Builder.

4. Specify a source folder for building Win PE ISO, i.e. the media drive with Win PE distribution or a folder with the distribution copy.

5. Locate a folder where you want to create Win PE ISO and provide the name for the ISO file.

6. Specify path to storage controller and NIC drivers that you want to add to Windows PE media. Click **Add** and specify the path to the necessary *.inf file for a corresponding SCSI, RAID, SATA controller or a network adapter. You will have to repeat this procedure for each driver you want to be included in the resulting Win PE boot media.

7. Check your settings in the summary screen and click **Proceed**.

8. Use any third-party tool that will burn ISO images to CD or DVD.




Media based on Win PE 2.0 and including Acronis True Image Echo Server requires at least 768MB RAM to work.

Chapter 10. Operations with archives

10.1 Validating backup archives

You can check the integrity of an archive to be certain that the archive is not damaged. Here's how to run a one-time validation task. For how to schedule regular archive validation, see *7.1 Creating scheduled tasks*.

1. To start the **Backup Archive Validation Wizard**, select **Validate Backup Archive** in the main window or in the **Tools** group or click **Validate Backup Archive** on the toolbar.
2. Select the archive to validate. If the archive is located in Acronis Secure Zone, select it to choose the archive at the next step.



3. Click **Proceed** to launch the validation procedure. After the validation is complete, you will see the results window. You can cancel checking by clicking **Cancel**.



You must have all incremental and differential backups belonging to the archive and the initial full backup to check archive data integrity. If any successive backups are missing, validation is not possible.



Please note: if you are logged in as an administrator and decide to validate the Backup Server archives, the validation operation will affect all the archives created by all the accounts at the Backup Server, which can be a very time-consuming process.

10.2 Exploring archives and mounting images

Acronis True Image Echo Server offers two kinds of archive contents management: mounting for images and exploring for both images and file-level archives.

Archives located on an FTP server cannot be explored or mounted.

Both operations are performed through the **Backup Archives** category.

Exploring images and file-level archives lets you view their contents and copy the selected files to the hard disk.

Mounting images as virtual drives lets you access them as though they were physical drives. This means that:

- a new disk with its own letter will appear in the drives list
- using Windows Explorer and other file managers, you can view the image contents as if they were located on a physical disk or partition
- you will be able to use the virtual disk in the same way as the real one: open, save, copy, move, create, delete files or folders. If necessary, the image can be mounted in read-only mode

Please keep in mind that although both file archives and disk/partition images have a default ".tib" extension, only **images** can be mounted. If you want to view file archive contents, use the Explore operation. The following is a brief summary of the Explore and Mount operations:

	Explore	Mount
Archive type	File-level, disk or partition image	Partition image
Assigning a letter	No	Yes
Archive modification	No	Yes (in R/W mode)
Files extraction	Yes	Yes




Acronis True Image Echo Server can mount or explore an image archive only if all its volumes reside in the same directory. If your archive spans several CD-R/RW discs and you want to mount the image, copy all volumes to a hard disk drive or network drive.

10.2.1 Exploring an archive


1. Click **Explore and Validate Backup Archives** in the **Tools** group or select the **Backup Archives** category on the sidebar to navigate to the Manage Backup Archives window. Then select **Explore Backup Archive**. Or, you can select **Tools -> Explore Backup Archive** in the main program menu.

2. Select an archive from the drive tree and click **Open**. If the archive is located in Acronis Secure Zone, select it to choose the archive at the next step.



If you added a comment to the archive, it will be displayed to the right of the drives tree. If the archive was protected with a password, Acronis True Image Echo Server will ask for it. Further steps will not be enabled until you enter the correct password.

3. The program opens a Windows Explorer window displaying the archive contents. If you selected an archive containing incremental or differential backups, Acronis True Image Echo Server will suggest that you select one of the successive backups by its creation date/time. This allows you to explore the data state for a given point in time.



To explore an incremental backup, you must have all previous incremental backups and the initial full backup. If any successive backups are missing, exploring is not possible.


To explore a differential backup, you must have the initial full backup as well.

Double-click the backup icon to view the data saved in the backup. You can copy and paste or drag-and-drop any file or folder from the backup being explored to any hard disk folder.

10.2.2 Mounting an image

1. Start the **Mount Image Wizard** by selecting **Operations -> Mount Image** in the main program menu.

2. Select the archive from the drives tree. If the archive is located in the Acronis Secure Zone, select it to choose the archive.



If you added a comment to the archive, it will be displayed to the right of the drives tree. If the archive was protected with a password, Acronis True Image Echo Server will ask for it. Neither the partitions layout, nor the **Next** button will be enabled until you enter the correct password.

3. If you selected an archive containing incremental images, Acronis True Image Echo Server will suggest that you select one of the successive incremental images by its creation date/time. This allows you to explore the partition state for a given point in time.




To mount an incremental image, you must have all previous incremental images and the initial full image. If any of the successive images are missing, mounting is not possible.

To explore a differential backup, you must have the initial full backup as well.

4. Select a partition to mount. (Note that you cannot mount the entire disk.)

You can also select a letter to be assigned to the virtual drive from the **Drive letter** drop-down list. If you do not want to assign a letter to the virtual drive, select **Do not assign**.



5. Select whether you want to mount image in **Read-only** or **Read/Write** mode.
6. If you select **Read/Write** mode, the program assumes that the connected image will be modified, and creates an incremental archive file to capture the changes. It is strongly recommended that you list the forthcoming changes in the comment to this file.
7. The program displays a summary containing a single operation. Click **Proceed** to connect the selected partition image as a virtual disk.
8. After the image is connected, the program will run Windows Explorer, showing its contents. Now you can operate with files or folders as if they were located on a physical disk.

You can connect multiple partition images. If you want to connect another partition image, repeat the procedure.

10.2.3 Unmounting an image

We recommend that you unmount the virtual disk after all necessary operations are finished, as keeping up virtual disks takes considerable system resources. If you do not, the virtual disk will disappear after your server is turned off.

To disconnect the virtual disk, click **Unmount Image** and select the disk to unmount. You can also unmount the disk in Windows Explorer by right-clicking on its icon and selecting **Unmount**.

10.3 Consolidating backups


The file name-based consolidation allows deleting the backups that you do not need any more from any archive while keeping the archive consistency.

Acronis True Image Echo Server can perform this operation in standalone (rescue) mode as well as under Windows control.

To consolidate backups in the archive:

1. Start the **Backup Consolidation Wizard** by selecting **Tools -> Consolidate archive** in the main program menu.

2. Select the archive from the drives tree. The file name-based consolidation does not support Acronis Secure Zone, so it is not displayed in the tree. For a backup consolidation in Acronis Secure Zone, see *8.4 Managing backups in the Acronis Secure Zone*.




An archive MyBackup consisting of one full (MyBackup) and four incremental backups (MyBackup2-5) is selected

3. The program displays a list of backups belonging to the selected archive with the backups creation date and time. The list is similar to that in the restore wizard. The upper backup is the full backup; the rest are incremental backups. Select the backups you want to *keep*.




Editing images, mounted in R/W mode, results in creating incremental backups, that are a kind of offshoots of the incremental chain. Therefore, they cannot be consolidated and always will be excluded from the archive copy.



The clone archive will consist of MyBackup3 and MyBackup5, however, their numbers will be zero (no number) and 2. MyBackup3 will change into a full backup

4. Choose location and name for the archive copy. By default, the program suggests the same location and the source archive name with (1) added.




New archive will be created in the same folder and named MyBackup(1)

5. The program displays the summary window. Click **Proceed** to start consolidation.

In our example, when consolidation is completed, the folder Backups will contain two archives MyBackup and MyBackup(1). The first is the source archive, the second is the copy consisting of MyBackup(1) and MyBackup(1)2.

MyBackup(1) is a full backup containing data as of Tuesday, July 17, 2007, 5:35:09 PM. MyBackup(1)2 is an incremental backup containing data as of Tuesday, July 17, 2007,

6:54:40 PM. You can make sure of this by starting the consolidation wizard again, selecting the archive MyBackup(1) and proceeding to the next window.



The resulting archive contents


Chapter 11. Notifications and event tracing

Sometimes a backup or restore procedure can last for 30 minutes or more. Acronis True Image Echo Server can notify you when it is finished through the WinPopup service or e-mail. The program can also duplicate messages issued during the operation or send you the full operation log after operation completion.

By default all notifications are **disabled**.

11.1 Email notification

To set up e-mail notification, select **Tools -> Options -> Notifications -> E-mail**:



Provide the e-mail address to which notifications will be sent. You can enter several addresses separated by semicolons.

Provide the outgoing SMTP server name. A user name and a password might also be needed if the SMTP server requires authentication.

Some Internet service providers require authentication on the incoming mail server before being allowed to send anything. If this is your case, click **Advanced** and tick off **Log on to incoming mail server** and provide the server name.

Filling up the **From** and **Subject** fields will help the e-mail client program filter notifications to the appropriate folder. If the From field is left blank, messages will be constructed as if they are from the destination address.

Below, in this window, you can choose whether you want to get notifications:

- when the operation is completed successfully (check **Add full log to the notification** to add the full operation log to the message)
- when the operation failed (check **Add full log to the notification** to add the full operation log to the message)
- during the operation when user interaction is required.

11.2 WinPopup notification


To set up WinPopup notification:

1. Enable the Messenger service on both the computer executing the task and the computer that will receive messages.



The Messenger service is disabled by default in Windows Server 2003 family. Change the service **Startup mode** to **Automatic** and start the service.

2. Select **Tools -> Options -> Notifications -> Windows Messenger (WinPopup)**:



Provide the name of the computer to which notifications will be sent.

Below in this window you can choose whether you want to get notifications:


- when the operation is completed successfully
- when the operation failed
- during the operation when user interaction is required.

11.3 Viewing logs

Acronis True Image Echo Server allows users to view its working logs. These logs can provide information about scheduled tasks results, including reasons for failure, if any.

To view the log window, select **Show log** on the toolbar or from the **Tools** menu.

The log browsing window contains two panes: the left one features the log list, while the right one shows selected log contents.



The left panel can contain up to 50 logs. If there are more, you can browse the list using the **More** and **Less** buttons with the left and right arrows.

To delete a log, select it and click **Delete**.

If any step was terminated by an error, the corresponding log will be marked with a red circle with a white "X" inside.

The right window features the list of steps contained in the selected log. The three buttons to the right control message filters: the white "X" in the red circle filters error messages, the exclamation sign in a yellow triangle filters warnings, and the "i" in the blue circle filters information messages.

To select columns (step parameters) to display, right-click the headers line or left-click the **Choose Details** button. Then check the desired parameters.

To sort messages by a particular parameter, click its header (click again to reverse order) or the **Arrange Icons by** button (the second from the right) and select the desired parameter.

You can also change column width by dragging the borders with a mouse.

11.4 Event tracing

11.4.1 Windows event log

You can choose whether to store event log messages issued by Acronis True Image Echo Server to Windows Event Log (to see this log, run **eventvwr.exe** or select **Control Panel -> Administrative tools -> Event Viewer -> Application**).

The default setting – **Do not save messages**

To change this setting, select **Tools -> Options -> Windows event log**.


An additional choice is available - recording **All events, Warnings and Errors**, or **Errors only**.

11.4.2 SNMP notifications

Acronis True Image Echo Server can provide the following Simple Network Management Protocol (SNMP) objects to SNMP management applications:

1.3.6.1.4.1.24769.100.200.1.0 - string identifying a type of occurred event (Information, Warning, Error)

1.3.6.1.4.1.24769.100.200.2.0 - string containing text description of occurred event (it looks identically to messages published by Acronis True Image Echo Server in its log).



Sending SNMP messages is disabled by default. To set up sending messages, select **Send messages to SNMP server** and specify:

- types of events to be reported: All events, Warnings and Errors, or Errors only
- name or IP address of the host running the SNMP management application, to which notifications will be sent
- name of SNMP community to which both the host running SNMP management application and the computers executing the task belong.

11.5 Managing System Restore

Microsoft Windows System Restore tool, available in Windows XP and Windows Vista operating systems, is used to undo harmful changes to the system without losing recently changed or created user data. To run the System Restore tool or find out more about it, select **Start -> Programs -> Accessories -> System Tools -> System Restore**.

If you run Acronis True Image Echo Server regularly, this feature in your operating system is redundant. You can turn it off, freeing up to 12% of your hard disk space, directly from Acronis True Image Echo Server.

1. To start the **System Restore Management Wizard**, click the **Manage System Restore** icon in the main program window.

2. Click **Next**.

3. Now you can turn on/off System Restore on all your hard disk(s) partitions at once or do it individually for each partition.



Note that you cannot turn off System Restore on the system disk (partition), yet keep it on other disks (partitions).

4. Click **Next**.

5. The program lists the configured changes. You can click **Back** to choose different settings. If you click **Cancel**, all new settings will be lost. Click **Proceed** to apply the changes.



If you turn off System Restore on any disk or partition, all previously created restore points for that disk (partition) will be deleted. Please make sure you do not need those restore points before proceeding.

Chapter 12. Working with a virtual environment

Virtual machine technologies provide a powerful tool to help accelerate the development, testing, deployment and support of PC applications.

As with physical machines, virtual machine (VM) data needs to be backed up periodically to prevent its loss due to hardware failure or human errors. Since more and more organizations choose running their business processes in a virtual environment, they need a solution to perform the data backup and restore on virtual machines. This chapter covers how Acronis True Image Echo Server can be used in virtual and heterogeneous environments.

12.1 Backing up data on virtual machines

A **virtual machine** is an emulated computer running within a host operating system. The software that emulates the computer is called the **virtualization software**. The most popular types of virtualization software are VMware Server and VMware Workstation, Microsoft Virtual Server and Microsoft Virtual PC, Citrix XenServer and Parallels Workstation.

Generally, a virtual machine can be treated:

1. As a physical computer (when it is online). Most Acronis True Image Echo Server features and settings are applicable to a VM. The backup procedure is almost the same (see details in *Chapter 5. Creating backup archives*).
2. As a set of files that change in line with the VM state. The files represent the VM configuration, storage, memory or other parameters. The files can be backed up with both imaging and file-level backup.

Acronis True Image Echo Server supports VMware Consolidated backup available in VMware Infrastructure 3. This application takes snapshots of virtual machines and uploads them to the proxy server. This enables LAN-free VM backup from the server rather than directly from ESX server.



Microsoft Virtual Server 2005 R2 SP1 has the Virtual Server Volume Shadow Copy Service (VSS) writer (VS Writer), which takes the VM snapshot by the backup software request. Support for the VS writer may be considered in future Acronis True Image Server versions.

If you plan to back up the virtual machine files, stop or suspend the virtual machine. Since the virtual disk file changes from session to session and therefore will be always included in the backup, incremental or differential backups are not appropriate in this case. An incremental backup size will be almost equal to a full backup size.

12.2 Recovering data on virtual machines

A virtual disk can be restored from its image (.tib file), previously created with Acronis True Image Echo Server just as physical disk can be recovered.

If the virtual machine cannot start, boot it into Acronis rescue environment using physical bootable media or RIS server, or by adding the bootable media ISO to the virtual machine. Another option is to create a new virtual machine with same configuration and disk size as the imaged machine and recover data to this disk.

The procedure is the same as with physical machines. See details in *Chapter 6. Restoring the backup data*.

The alternative way of recovering a VM is by converting the image (.tib) file to a virtual disk file of appropriate format and adding this disk to the VM. This is the easiest way to recover data on a virtual machine.

12.3 Using the disk conversion feature

A virtual hard disk is a file that provides storage for a virtual machine. Different virtualization software use different virtual disk format and therefore the file extension.

Acronis True Image Echo Server has the ability to convert a disk image, created with the program (.tib), to a virtual disk file of the type you select (.vmdk, .pvs, and .vhd). You will then be able to add the disk to a virtual machine of compatible type: **VMware, Microsoft virtual machine (MS Virtual PC, MS Virtual Server, MS Hyper-V), Parallels virtual machine** and **Citrix XenServer**, respectively. The further usage of the disk is as follows.

12.3.1 Recover data on the VM

In case data is corrupted or inadvertently deleted while the VM is running, do one of the following:

- add the converted disk, either system or non-system, to the VM, copy the needed data to the original disk, then remove the converted disk, or
- add the converted disk, either system or non-system, to the VM and use the data contained on the disk.

12.3.2 Recover both data and the VM

In case the VM cannot start, do one of the following:

- add the converted system disk to the VM and remove the corrupted disk, or
- create a new VM with the converted system disk, or
- add the disk to the previously created machine clone (this allows replacing the machine on the network in seconds because you need not configure a new VM).

12.3.3 Physical to virtual migration

Physical disks images can be converted to virtual disks as well as virtual disks images.

A Windows system image will be supplemented with appropriate system drivers during conversion, so that Windows could boot up on the VM. (In fact, the Acronis Universal Restore technology is applied in background because the program is aware which drivers are needed for compatible virtual machines.)

The conversion operation enables five-step **physical to virtual** migration:

1. Create images of all (or some) physical machine disks, including the system disk.
2. Convert the images to virtual disks.
3. Create a new VM with the converted system disk.
4. Add the other converted disks to the VM.
5. Start the VM and complete the hardware drivers configuration, if Windows prompts.

This allows:

- the fastest replacement of the physical machine with the previously created virtual copy
- moving multiple workloads from legacy physical servers to virtual machines to reduce hardware maintenance and power consumption costs.

The alternative method of **physical to virtual** migration is by restoring a physical disk from an image to a virtual machine. The procedure is the same as with restoring physical machines.

To ensure booting up the system on the virtual machine, use Acronis Universal Restore. If the target virtual drive is a SCSI hard drive, provide appropriate drivers. For example, the VMware environment requires Buslogic or LSI logic drivers. Use drivers bundled with your virtualization software or download the latest drivers versions from the software manufacturer's website. For more information about the recovery procedure see *Chapter 6. Restoring the backup data*.

The inverse migration - **virtual to physical** - is done using common disk imaging and restoring:

1. Create images of all (or some) virtual machine disks, including the system disk.
2. Restore the images to physical disks. When restoring a system disk, use Acronis Universal Restore. Complete the hardware driver configuration if Windows prompts.

Combination of the two migration features gives you the flexibility to implement a lot of scenarios, for example:

- replace your physical server on the network with its virtual copy, while the server is recovered or upgraded
- test the new software or other changes you wish to make to the server on its virtual copy and then apply the changes to the physical server.

12.3.4 Converting workloads

You can convert workloads from one virtual technology to another through imaging virtual drives. For example, let's say your company uses Microsoft Virtual Servers, but you need to use VMware-based virtual appliances. This is easy to do with the conversion functionality. Again, a Windows system image will be supplemented with appropriate system drivers during conversion so that Windows could boot up on the another type of VM.

1. Create images of all (or some) virtual machine disks, including the system disk.
2. Convert the images to virtual disks of desired format.
3. Create a new VM of the desired type with the converted system disk.
4. Add the other converted disks to the VM.
5. Start the VM and complete the hardware driver configuration if Windows prompts.

12.4 Converting disk images to virtual disks

To convert a disk image to a virtual disk file:

1. Select **Tools -> Convert to Virtual Disk** in the main program menu.

2. Select the disk image to convert. If the image is located on an Acronis Backup Server or in the Acronis Secure Zone, select Personal backup location or Acronis Secure Zone, to select the image during the next step.

3. If there are several disks in the image, select one to convert.

4. Choose a type of the disk to be created.

5. Specify the path to the file to be created. The file can be directed to any storage supported by Acronis True Image Echo Server, except for the Acronis Secure Zone.

Since the disk space is not preallocated, the physical disk on which the virtual disk will run is expected to have sufficient space for the virtual disk to grow.

6. Click **Proceed** in the summary window.

Chapter 13. Transferring the system to a new disk

13.1 General information

Sooner or later computer users find that their hard disk is just too small. If you don't have space for more data, you can add another disk specifically for data storage.

For example, you might find that your hard disk does not have enough space for the operating system and installed applications, preventing you from updating your software. In this case, you have to transfer the system to a higher-capacity hard disk.

To transfer the system, you must first install the disk in the server. If a server doesn't have a bay for another hard disk, you can temporarily install it in place of your CD-ROM. If that is not possible, you can clone a hard disk by creating its image and restoring it to a new hard disk with larger partitions.

There are two transfer modes available: automatic and manual.

In the automatic mode, you will only have to take some simple actions to transfer all the data, including partitions, folders and files, to a newer disk, making it bootable if the original disk was bootable.

There will be only one difference between these disks – partitions on the newer disk will be larger. Everything else, including the installed operating systems, data, disk labels, settings, software and everything else on the disk, will remain the same.



This is the only result available in the automatic mode. The program can only duplicate the original disk layout to the new one. To obtain a different result, you will have to answer additional questions about cloning parameters.

The manual mode will provide additional data transfer flexibility.

1. You will be able to select the method of partition and data transfer:

- as is
- new disk space is proportionally distributed among the old disk partitions
- new disk space is distributed manually

2. You will also be able to select operations to perform on the old disk:

- leave partitions (and data) on the old disk
- remove all information from the old disk
- create new partitions on the old disk (and remove all the older information)



On program screens, damaged partitions are marked with a red circle and a white "X" inside in the upper left corner. Before you start cloning, you should check such disks for errors using the appropriate operating system tools.

13.2 Security

Please note the following: If the power goes out or you accidentally press **RESET** during the transfer, the procedure will be incomplete and you will have to partition and format or clone the hard disk again.


No data will be lost because the original disk is only being read (no partitions are changed or resized) until data transfer is completed.

We recommend that you do not delete data from the old disk until you are sure it is correctly transferred to the new disk, the server boots up from it and all applications work.

13.3 Executing transfers

13.3.1 Selecting Clone mode

You will see the **Clone mode** window just after the welcome window.




We recommend using automatic mode in most cases. The manual mode can be useful if you need to change the disk partition layout.

If the program finds two disks, one partitioned and another unpartitioned, it will automatically recognize the source disk as the partitioned disk and the destination disk as the unpartitioned disk, so the next two steps will be bypassed.

13.3.2 Selecting source disk


If the program finds several partitioned disks, it will ask you which is the source (i.e. the older data disk).



You can determine the source and destination using the information provided in this window (disk number, capacity, label, partition and file system information).

13.3.3 Selecting destination disk

After you select the source disk, select the destination where the disk information will be copied.




The previously selected source becomes grayed-out and disabled for selection.



If either disk is unpartitioned, the program will automatically recognize it as the destination and bypass this step.

13.3.4 Partitioned destination disk

At this point, the program checks to see if the destination disk is free. If not, you will be prompted by the **Nonempty Destination Hard Disk** window stating that the destination disk contains partitions, perhaps with data.



You will have to select between:

- **Delete partitions on the destination hard disk** – all existing partitions will be deleted during cloning and all their data will be lost.
- **No, I do not want to delete partitions** – no existing partition will be deleted, discontinuing the cloning operation. You will only be able to cancel this operation and return to select another disk.

To continue, select the first choice and click **Next**.



Note that no real changes or data destruction will be performed at this time! For now, the program will just map out cloning. All changes will be implemented only when you click **Proceed**.

13.3.5 Old and new disk partition layout

If you selected the automatic mode before, the program will ask you for nothing further. You will see the window graphically illustrating information (as rectangles) about the source disk (partitions and unallocated space) and the destination disk layout.

Along with the disk number, some additional information is provided: disk capacity, label, partition and file system information. Partition types — primary, logical — and unallocated space are marked with different colors.


Next you will see the cloning summary.

13.3.6 Old disk data

If you selected the manual mode, the program will ask you what to do with the old disk:

- **Create a new partition layout** – All existing partitions and their data will be deleted (but they will also be cloned to the new disk, so you won't lose them)

- **Keep data** – leave the old disk partitions and data intact
- **Destroy data** – destroy all data on the old disk.



If you are going to sell or give away your old disk, we recommend that you make sure you destroyed the data on it.


If you are going to keep it for data storage, you can create a new partition layout on it. In this case, the disk will be ready right after cloning is complete.

To protect yourself from unforeseen consequences, it would be better to leave the old disk data intact, as you will be able to delete it later.

13.3.7 Destroying the old disk data

If you elected to destroy the old disk data in the previous step, you will have to select the destruction method now:

- **Quick** – quick one-pass destruction
- **Normal** – multipass destruction




The second method takes more time, but makes it impossible to recover data afterwards, even with special equipment.

The first method is less secure, but is still suitable for most cases.

13.3.8 Selecting partition transfer method

Acronis True Image Echo Server will offer you the following data transfer methods:

- As is
- **Proportional** – the new disk space will be proportionally distributed among cloned partitions
- **Manual** – you will specify the new size and other parameters yourself



If you elect to transfer information "as is," a new partition will be created for every old one with the same size and type, file system and label. The unused space will become unallocated. Further, you will be able to use the unallocated space to create new partitions or to enlarge the existing partitions with special tools, such as Acronis Disk Director Suite.

As a rule, "as is" transfers are not recommended, as they leave much unallocated space on the new disk. Using the "as is" method, Acronis True Image Echo Server transfers unsupported and damaged file systems.

If you transfer data proportionally, each partition will be enlarged, according to the proportion of the old and new disk capacities.

FAT16 partitions are enlarged less than others, as they have a 4GB size limit.

Depending on the selected combination, you will proceed to either the old disk partitioning window, or the disk partition layout window (see below).

13.3.9 Partitioning the old disk

If you selected **Create a new partition layout** earlier in the process, it is now time to repartition your old disk.

During this step, you will see the current disk partition layout. Initially, the disk has unallocated space only. This will change when you create new partitions.


Having completed the required steps, you will add a new partition. To create another one, simply repeat those steps.

If you make a mistake, click **Back** to redo.

After you create the necessary partitions, uncheck the **Create new partition in unallocated space** box and click **Next**.

13.3.10 Old and new disk partition layouts

In the next window, you will see rectangles indicating the source hard disk, including its partitions and unallocated space, as well as the new disk layout.




Along with the hard disk number, you will also see disk capacity, label, partition and file system information. Different partition types, including primary, logical and unallocated space are marked with different colors.



If you selected manual partition creation earlier, the partition layout will look different. This partitioning method is described below.

13.3.11 Cloning summary

In the next window, you will see a list of briefly described operations to be performed on the disks.



Cloning a disk containing the currently active operating system will require a reboot. In that case, after clicking **Proceed** you will be asked to confirm the reboot. Canceling the reboot will cancel the entire procedure.

Cloning a non-system disk or a disk containing an operating system, but one that is not currently active, will proceed without reboot. After you click **Proceed**, Acronis True Image Echo Server will start cloning the old disk to the new disk, indicating the progress in a special window. You can stop this procedure by clicking **Cancel**. In that case, you will have to repartition and format the new disk or repeat the cloning procedure. After the operation is complete, you will see the results message.


13.4 Cloning with manual partitioning

13.4.1 Old and new disk partition layouts

The manual transfer method enables you to resize partitions on the new disk. By default, the program resizes them proportionally.

In the next window, you will see rectangles indicating the source hard disk, including its partitions and unallocated space, as well as the new disk layout.

Along with the hard disk number, you will see disk capacity, label, partition and file system information. Different partition types, including primary, logical and unallocated space are marked with different colors.



To resize either partition, check the **Proceed relayout** box. If you are satisfied with the partition layout shown, uncheck this box (if checked). Clicking **Next**, you will proceed to the cloning summary window.



Be careful! Clicking **Back** in this window will reset all size and location changes that you've selected, so you will have to specify them again.

First, select a partition to resize. It will be underlined in red.

Resize and relocate it on the next step.

You can do this by entering values to the **Unallocated space before**, **Partition size**, or **Unallocated space after** fields, by dragging the partition borders or by dragging the partition itself.

If the cursor turns to two vertical lines with left and right arrows, it is pointed at the partition border and you can drag it to enlarge or reduce the partition's size. If the cursor turns to four arrows, it is pointed at the partition, so you can move it to the left or right (if there's unallocated space near it).

Having provided the new location and size, click **Next**. You will be taken two steps back to the partition layout. You might have to perform some more resizing and relocation before you get the layout you need.


Chapter 14. Adding a new hard disk

If you don't have enough space for your data, you can either replace the old disk with a new, higher-capacity one (data transfers to new disks are described in the previous chapter), or add a new disk to store data, leaving the system on the old disk. If the server has space for another disk, it would be easier to add a data disk drive than to clone a system one.

To add a new disk, you must first install it in your server.

14.1 Selecting a hard disk

Select the disk that you've added to the server.



This window might be bypassed if the program detects the new disk itself. In this case, you will immediately proceed to the new partition creation.

If there are any partitions on the new disk, they must be deleted first.

Select **Delete partitions on the destination hard disk** and click **Next** to continue.

14.2 Creating new partitions

Next you will see the current partition layout. Initially, all disk space will be unallocated. This will change after you add new partitions.

To create a partition, select **Create new partition in unallocated space** and click **Next** to perform steps required by the partition creation wizard.

You will be prompted to set the new partition location and size. You can do this by entering values to the **Unallocated space before, Partition size, or Unallocated space after** fields, by dragging the partition borders or by dragging the partition itself.

If the cursor turns to two vertical lines with left and right arrows, it is pointed at the partition border and you can drag it to enlarge or reduce the partition size. If the cursor


turns to four arrows, it is pointed at the partition, so you can move it to the left or right (if there is unallocated space near it). Having provided the new partition location and size, you can input a label for the new partition.

If you make a mistake at partitioning, click **Back** to redo the process.

Finally, you will be taken back to the partition layout screen. Check the resulting partitions layout and start creating another partition or move on by unchecking **Create new partition in unallocated space** and clicking **Next**.

14.3 Disk add summary

The disk add summary contains a list of operations to be performed on disks.



After you click **Proceed**, Acronis True Image Echo Server will start creating and formatting new partitions, indicating the progress in a special window. You can stop this procedure by clicking **Cancel**. In that case, you will have to repartition and format the new disk or repeat the disk add procedure.

Chapter 15. Command-line mode and scripting

Acronis True Image Echo Server supports the command-line mode and enables backup automation by executing XML scripts.

The command-line mode functionality is somewhat limited as compared to the GUI mode. You will not be able to perform operations that require the reboot of the system, such as restore a system partition or clone a system drive. These operations only can be done through the GUI.

Scripting is intended only for backup.

15.1 Working in the command-line mode

An administrator might need a console interface in some situations. Acronis True Image Echo Server supports this mode with **TrueImageCmd.exe** utility as well as the **Ebasrvdb.exe** and **Adv_report.exe** tool.

TrueImageCmd.exe is located in the folder where Acronis True Image Echo Server has been installed, by default it is

C:\Program Files\Acronis\TrueImageEchoServer.

Ebasrvdb.exe is located in the folder where the Backup Server is installed, by default it is

C:\Program Files\Acronis\BackupServer

Adv_report.exe is located in

C:\Program Files\Common files\Acronis\AdvReport

15.1.1 TrueImageCmd.exe supported commands

TrueImageCmd has the following format:

```
trueimagecmd /command /option1 /option2...
```

Commands may be accompanied with options. Some options are common for most trueimagecmd commands, while other are specific for individual commands. Below is a list of supported commands and compatible options.

Command	Common Options	Specific Options
create Creates an image of specified disks and partitions	/filename:[file name] /password:[password] /asz /net_user:[username] /net_password:[password] /ftp_user /ftp_password /incremental /differential /compression:[0...9] /split:[size in MB] /oss_numbers /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	/harddisk:[disk number] /partition:[partition number] /file_partition:[partition letter] /raw /progress:[on off]
filebackup	/filename:[file name]	/include:[names]

Backs up specified files and folders	/password:[password] /asz /net_user:[username] /net_password:[password] /ftp_user /ftp_password /incremental /differential /compression:[0...9] /split:[size in MB] /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	/exclude_names:[names] /exclude_masks:[masks] /exclude_system /exclude_hidden
deploy Restores disks and partitions, except for the MBR, from an image	/filename:[file name] /password:[password] /asz /index:N /net_user:[username] /net_password:[password] /ftp_user /ftp_password /oss_numbers /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	/harddisk:[disk number] /partition:[partition number] /target_harddisk:[disk number] /target_partition:[partition number] /file_partition:[partition letter] /start:[start sector] /fat16_32 /size:[partition size in sectors] /type:[active primary logical] /preserve_mbr When using the Acronis Universal Restore option: /ur_path:[path] /ur_username:[user] /ur_password:[pwd] /ur_driver:[inf-filename]
deploy_mbr Restores the MBR from a disk or partition image	/filename:[file name] /password:[password] /asz /index:N /net_user:[username] /net_password:[password] /ftp_user /ftp_password /oss_numbers /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	/harddisk:[disk number] /target_harddisk:[disk number]
filerestore Restores files and folders from a file archive	/filename:[file name] /password:[password] /asz /index:N /net_user:[username] /net_password:[password] /ftp_user /ftp_password /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	/target_folder:[target folder] /overwrite:[older never always] /restore_security:[on off] /original_date:[on off]
verify Verifies the archive data integrity	/filename:[file name] /password:[password] /asz /net_user:[username] /net_password:[password] /ftp_user /ftp_password /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]	
pit_info Displays the numbered list of backups, contained in the specified archive	/filename:[file name] /password:[password] /asz /net_user:[username] /net_password:[password] /ftp_user /ftp_password	

<p>consolidate</p> <p>Creates a consistent copy of the archive which will contain only the specified backups</p>	<pre>/filename:[file name] /password:[password] /ftp_user /ftp_password /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]</pre>	<pre>/target_filename:[file name] /include_pits:[pits numbers] /net_src_user:[username] /net_src_password:[password] /net_user:[username] /net_password:[password]</pre>
<p>convert</p> <p>Converts an image to virtual disk format for using with a virtual machine</p>	<pre>/filename:[file name] /password:[password] /asz /index:N /net_user:[username] /net_password:[password] /ftp_user /ftp_password /log:[file name] /log_net_user:[remote user] /log_net_password:[password]</pre>	<pre>/target_filename:[file name] /harddisk:[disk number] /vm_type:[vmware esx microsoft parallels] /ur /ur_path:[path]</pre>
<p>list</p> <p>Lists available drives and partitions. With the filename option; lists the image contents</p>	<pre>/password:[password] /index:N /asz /net_user:[username] /net_password:[password] /ftp_user /ftp_password</pre>	<pre>/filename:[file name]</pre>
<p>explore</p> <p>Connects an image as a virtual drive</p>	<pre>/filename:[file name]* /password:[password] /asz /index:N /net_user:[username] /net_password:[password] /log:[file name] /log_net_user:[remote user] /log_net_password:[password] *for a split image, the name of the last created file</pre>	<pre>/partition:[partition number] /letter:X</pre>
<p>unplug</p> <p>Disconnects the image connected as a virtual drive</p>		<pre>/letter:X /letter:all</pre>
<p>asz_create</p> <p>Creates the Acronis Secure Zone on the selected drive</p>	<pre>/password:[password] /oss_numbers /reboot /log:[file name] /log_net_user:[remote user] /log_net_password:[password]</pre>	<pre>//harddisk:X /partition:[partition number] /size:[ASZ size in sectors] unallocated /asz_activate</pre>
<p>asz_activate</p> <p>Activates the Acronis Startup Recovery Manager</p>	<pre>/password:[password]</pre>	
<p>asz_content</p> <p>Displays the Acronis Secure Zone size, free space and contents</p>	<pre>/password:[password]</pre>	
<p>asz_files</p> <p>Displays the Acronis</p>	<pre>/password:[password]</pre>	

Secure Zone size, free space and contents using the generated file names		
asz_delete_files Deletes the most recent backup in the archive located in the Acronis Secure Zone	/filename: [file name] /password: [password] /log: [file name] /log_net_user: [remote user] /log_net_password: [password]	
asz_delete Deletes the Acronis Secure Zone	/password: [password] /oss_numbers /reboot /log: [file name] /log_net_user: [remote user] /log_net_password: [password]	/partition: [partition number]
clone Clones a hard disk	/reboot	/harddisk: [disk number] /target_harddisk: [disk number]
help Shows usage		

15.1.2 Common options (options common for most trueimagecmd commands)

Option	Description	Archive location
Access to archives		
/filename: [file name]	Backup file name	Other than ASZ
	Archive name (when restoring or deleting files from ASZ). Can be obtained with asz_files)	ASZ
/password: [password]	Specify the password for the archive (if required)	Other than ASZ
	Specify the password for the ASZ (if required)	ASZ
/asz: [number of archive]	Addresses to the ASZ and selects the archive (a full backup with or without increments). To get the archive number, use /asz_content	ASZ
/index:N N = Number of the backup in an archive: 1 = basic full backup 2 = 1st increment... and so on 0 (default) = latest increment	Selects a backup in a sequence of incremental backups inside the archive. To get a backup index from the ASZ, use /asz_content	Any
/net_user: [username]	Specify a user name for network drive access	Network drive
/net_password: [password]	Specify a password for network drive	Network drive

	access	
/ftp_user: [username]	Specify a user name for access to an FTP server	FTP server
/ftp_password: [password]	Specify a password for access to an FTP server	FTP server
Backup options		
/incremental	Set the backup type to incremental. If not specified or there is no basic full backup, a full backup will be created	Any
/differential	Set the backup type to differential. If not specified or there is no basic full backup, a full backup will be created	Any
/compression: [0...9]	Specify the data compression level. It ranges from 0 to 9 and is set to 3 by default	Any
/split: [size in MB]	Split the backup into parts of the specified size	Other than ASZ
General options		
/oss_numbers	Declares that numbers of partitions in the /partition option are adjusted for the MBR partition table rather than just as ascending numbers. This means that primary partitions have numbers 1-1, 1-2, 1-3, 1-4; logical partitions numbers start with 1-5. For example, if the disk has one primary and two logical partitions, their numbers can appear as follows: /partition:1-1,1-2,1-3 or /oss_numbers /partition:1-1,1-5,1-6	Any
/reboot	Reboot the server after the operation is completed	Any
/log: [file name]	Create a log file of the current operation with the specified file name	Any
/log_net_user: [remote user]	If the log file is created on a network share, include the user name for logon to the share	Any
/log_net_password: [password]	If the log file is created on a network share, include the password for logon to the share	Any

15.1.3 Specific options (options specific for individual trueimagecmd commands)

Option	Description
create	
/harddisk: [disk number]	Specifies the hard disks to include into the image file. The list of available hard disks is provided by the /list command. An image

	<p>may contain data of more than one hard disk. In that case, separate disk numbers by commas, e.g.:</p> <pre>/harddisk:1,3</pre> <p>By specifying</p> <pre>/harddisk:DYN</pre> <p>you will back up all dynamic volumes present in the system.</p>
<code>/partition:[partition number]</code>	<p>Specifies the partitions to include into the image file. The list of available partitions is provided by <code>/list</code>. Partition numbers are specified as <disk number>-<partition number>, e.g.:</p> <pre>/partition:1-1,1-2,3-1</pre> <p>Dynamic volumes are specified with prefix DYN, e.g.:</p> <pre>/partition:DYN1,DYN2</pre>
<code>/file_partition:[partition letter]</code>	<p>Specifies the partition where the image file will be stored (by letter or number). This option is used with <code>/filename:[file_name]</code>. In that case the file name must be specified without drive letter or root folder. For example:</p> <pre>/file_partition:D /filename:"\1.tib"</pre> <p>Dynamic volumes are specified with prefix DYN, e.g.:</p> <pre>/file_partition:DYN1 /filename:"\1.tib"</pre>
<code>/raw</code>	<p>Use this option to create an image of a disk (partition) with an unrecognized or unsupported file system. This will copy all disk/partition contents sector-by-sector. Without this option only the sectors containing useful system and user data are imaged (for the supported file systems).</p>
<code>/progress:[on off]</code>	<p>Shows/hides the progress information (percent completed). It is shown by default.</p>
Filebackup	
<code>/include:[names]</code>	<p>Files and folders to be included in the backup (comma separated). For example:</p> <pre>/include:E:\Workarea\MyProject</pre>
<code>/exclude_names:[names]</code>	<p>Files and folders to be excluded from the backup (comma separated). For example:</p> <pre>/exclude_names:E:\Workarea\MyProject\111.doc,E:\Workarea\MyProject\Old</pre>
<code>/exclude_masks:[masks]</code>	<p>Applies masks to select files to be excluded from the backup. Use the common Windows masking rules. For example, to exclude all files with extension .exe, add *.exe. My???.exe will exclude all .exe files with names consisting of five symbols and starting with "my":</p> <pre>/exclude_masks:*.txt,111.*</pre>
<code>/exclude_system</code>	<p>Excludes all system files from the backup.</p>
<code>/exclude_hidden</code>	<p>Excludes all hidden files from the backup.</p>
Deploy	
<code>/file_partition:[partition letter]</code>	<p>Specifies the partition where the image file is stored (by letter or number). This option is used with <code>/filename:file_name</code>. In this case the file name must be specified without drive letter or root</p>

	<p>folder. For example:</p> <pre>/file_partition:D /filename:"\1.tib"</pre> <p>Dynamic volumes are specified with prefix DYN, e.g.:</p> <pre>/file_partition:DYN1 /filename:"\1.tib"</pre>
/harddisk:[disk number]	Specifies the basic hard disks to restore.
/partition:[partition number]	Specifies the partitions to restore. Dynamic volumes are specified with prefix DYN, e.g.:
	<pre>/partition:DYN1</pre>
/target_harddisk:[disk number]	Specifies the hard disk number where the image will be restored. By specifying
	<pre>/target_harddisk:DYN</pre> you will select unallocated space on all dynamic disks that present in the system.
/target_partition:[partition number]	Specifies the target partition number for restoring a partition over the existing one. If the option is not specified, the program assumes that the target partition number is the same as the partition number specified with the /partition option. Dynamic volumes are specified with prefix DYN, e.g.:
	<pre>/target_partition:DYN1</pre>
/start:[start sector]	Sets the start sector for restoring a partition to the hard disk unallocated space.
/size:[partition size in sectors]	Sets the new partition size (in sectors).
/fat16_32	Enables the file system conversion from FAT16 to FAT32 if the partition size after recovery is likely to exceed 2GB. Without this option, the recovered partition will inherit the file system from the image.
/type:[active primary logical]	<p>Sets the restored partition active, primary or logical, if possible (for example, there cannot be more than four primary partitions on the disk.) Setting a partition active always sets it primary, while a partition set primary may stay inactive.</p> <p>If the type is not specified, the program tries to keep the target partition type. If the target partition is active, the restored partition is set active. If the target partition is primary, and there are other primary partitions on the disk, one of them will be set active, while the restored partition becomes primary. If no other primary partitions remain on the disk, the restored partition is set active.</p> <p>When restoring a partition on unallocated space, the program extracts the partition type from the image. For the primary partition, the type will be set as follows:</p> <ul style="list-style-type: none"> - if the target disk is the 1st according to BIOS and it has not other primary partitions, the restored partition will be set active - if the target disk is the 1st according to BIOS and there are other primary partitions on it, the restored partition will be set logical - if the target disk is not the 1st, the restored partition will be set logical.
/preserve_mbr	When restoring a partition over an existing one, the target partition is deleted from the disk along with its entry in the target disk MBR.

	Then, with the <code>/preserve_mbr</code> option, the restored partition's entry will occupy the upper empty position in the target disk MBR. Thus, the target disk MBR is preserved. If not specified, the restored partition's entry will occupy the same position as in the source disk MBR saved in the image. If the position is not empty, the existing entry will be moved to another position.
The following options are available when using the Acronis Universal Restore add-on to Acronis True Image Echo Server. For more information see <i>3.6 Acronis Universal Restore</i> .	
<code>/ur_path: [path]</code> <code>/ur_username: [user]</code> <code>/ur_password: [pwd]</code>	Specifies using Acronis Universal Restore and the path to the drivers storage.
<code>/ur_driver: [inf-filename]</code>	Specifies using Acronis Universal Restore and the mass-storage driver to be installed.
Filerestore	
<code>/target_folder: [target folder]</code>	Specifies a folder where folders/files will be restored (a target folder). If not specified, the original path is re-created from the archive.
<code>/overwrite: [older never always]</code>	This option allows you to keep useful data changes made since the backup being restored was done. Choose what to do if the program finds in the target folder a file with the same name as in the archive: <code>older</code> – this will give the priority to the most recent file modification, whether it be in the archive or on the disk. <code>never</code> – this will give the file on the hard disk unconditional priority over the archived file. <code>always</code> – this will give the archived file unconditional priority over the file on the hard disk. If not specified, the files on the disk will <code>always</code> be replaced with the archived files.
<code>/restore_security: [on off]</code>	Specifies whether to restore files' security attributes (default) or the files will inherit the security settings of the folder where they will be restored.
<code>/original_date: [on off]</code>	Specifies whether to restore files' original date and time from the archive or assign the current date and time to the restored files. If not specified, the current date is assigned.
Consolidate	
<code>/target_filename: [file name]</code>	Specifies the path to and name of the archive copy to be created. If there are two or more backups (pits) in the copy, numbers will be added to their names.
<code>/include_pits: [pits numbers]</code>	Specifies the backups (pits) to be included in the archive copy. To get the numbers of pits, use <code>/pit_info</code> . Separate multiple values with semicolon, for example: <code>/include_pits:2,4,5</code>
<code>/net_src_user: [username]</code>	Specifies the username for logon to network share to access the source archive
<code>/net_src_user: [password]</code>	Specifies the password for logon to network share to access the source archive

<code>/net_user: [username]</code>	Specifies the username for logon to network share to save the resulting archive
<code>/net_user: [password]</code>	Specifies the password for logon to network share to save the resulting archive
Convert	
<code>/target_filename: [file name]</code>	Specifies the path to and name of the virtual disk file to be created. The file extension corresponds to the type of the virtual machine to which the virtual disk will be added: VMware virtual machine - .vmdk MS virtual machine and Citrix XenServer - .vhd Parallels virtual machine - .hdd.
<code>/harddisk: [disk number]</code>	Specifies the hard disks to convert by numbers. For each disk, a separate virtual disk will be created. By specifying <code>/harddisk:DYN</code> you will convert all dynamic volumes that present in the system.
<code>/vm_type: [vmware esx Micro soft parallels]</code>	The type of the virtual machine to which the virtual disk will be added.
<code>/ur</code>	Use when converting image of a disk, containing Windows, and the resulting virtual disk is supposed to be bootable. With this key, the program will add drivers, necessary for the virtual machine type selected with <code>/vm_type</code> key, to the resulting virtual disk. If the image was taken from a virtual machine of the same type, normally the key is not needed. Drivers for the virtual machine reside in the storage, defined by the registry <code>HKEY_LOCAL_MACHINE\SOFTWARE\Acronis\UniversalRestore\Drive rsPackPath</code> . In case the storage has been moved, please change the key or use the command <code>/ur_path: [path]</code> .
<code>/ur_path: [path]</code>	The same as <code>/ur</code> with custom path to the virtual machine drivers storage.
List	
<code>/filename: [file_name]</code>	With this option, the image contents is displayed. When listing image contents, partition numbers may not coincide with those in the drives/partitions list, if the image does not contain all the disk partitions. For example, if the image contains partitions 2-3 and 2-5, they will be listed as 2-1 and 2-2. If the <code>deploy /partition</code> command cannot find a partition in the image by its physical number, use <code>/partition:<number in the image> /target_partition:<physical number of the target partition></code> keys. For the above example, to restore partition 2-5 to its original place use: <code>/partition:2-2 /target partition:2-5.</code>
Explore	
<code>/partition: [partition number]</code>	Specifies a list of partitions to be mounted as virtual drives. Without this option, all partitions stored in the image will be mounted. To obtain the partition number for this option, list the image

	contents with the <code>/list/filename</code> command and use the number from the <code>Idx</code> column.
<code>/letter</code>	Assigns letters to the mounted drives. This option is used with <code>/partition</code> option only.
Unplug	
<code>/letter:X</code>	Specifies the virtual drive to be disconnected by letter.
<code>/letter:all</code>	Disconnects all virtual drives.
asz_create	
<code>/password:[password]</code>	Sets a password for the Acronis Secure Zone.
<code>/harddisk:X</code>	Specifies the hard disk number where the Acronis Secure Zone will be created.
<code>/size:[ASZ size in sectors unallocated]</code>	<p>Sets the Acronis Secure Zone size (in sectors). If not specified, the size is set as an average between the maximal (unallocated space plus free space on all partitions selected with the <code>/partition</code> option) and minimal (about 35MB) values. Either way, the program will first use the unallocated space. If there is not enough unallocated space, the selected partitions will be decreased. Resizing of locked partitions requires a reboot. With "unallocated", the zone will use all unallocated space on the disk. Partitions will be moved, if necessary, but not resized. Moving of locked partitions requires a reboot. The <code>/partition</code> option is ignored.</p>
<code>/asz_activate</code>	Activates the Acronis Startup Recovery Manager. The option will not take effect if the system partition is resized during Acronis Secure Zone creation. In that case, use the separate <code>/asz_activate</code> command.
asz_activate	
<code>/password:[password]</code>	Specifies a password for the Acronis Secure Zone.
asz_delete	
<code>/partition:[partition number]</code>	Specifies partitions to which free space will be added after the Acronis Secure Zone is deleted. If you specify several partitions, the space will be distributed proportionally to each partition's size.
clone	
<code>/harddisk:[disk number]</code>	Specifies a source hard disk which will be cloned to the new hard disk.
<code>/target_harddisk:[disk number]</code>	Specifies the target hard disk number where the source hard disk will be cloned.

15.1.4 Trueimagecmd.exe usage examples

1. Image disks and partitions

```
trueimagecmd /create /filename:"C:\Test\1.tib" /partition:2-1,1-3
```

-
- This will create an image named 1.tib of the partitions 2-1 and 1-3. The image will be saved to the C:\Test\ folder.

```
trueimagecmd /create /asz /partition:2-1,1-3
```

- This will create an image of the partitions 2-1 and 1-3 in the Acronis Secure Zone.

```
trueimagecmd /create /filename:"\Test\1.tib" /partition:2-1,1-3 /file_partition:3-1
```

- This will create an image named 1.tib of the partitions 2-1 and 1-3. The image will be saved in the folder \Test on partition 3-1.

```
trueimagecmd /create /filename:"C:\Test\1.tib"  
/password:qwerty /harddisk:2 /reboot /raw /incremental  
/compression:5 /split:640 /progress:off
```

- This will append an incremental image to the image named 1.tib of hard disk 2. The image will be saved to C:\Test\ folder, protected with password "qwerty", split into parts of 640MB, and contain all cluster data. Image compression level is 5. The server will be rebooted after the operation is completed.

```
trueimagecmd /create /partition:2-1  
/filename:\\server1\folder\arc.tib /net_user:user1  
/net_password:pw1 /log:\\server2\dir\log1.log  
/log_net_user:user2 /log_net_password:pw2
```

- This will create an image of partition 2-1 named arc.tib in the shared folder \\server1\folder. The operation log file log1.log will be saved on another share \\server2\dir. Credentials for both shares are provided.

```
trueimagecmd /create /partition:2-1  
/filename:ftp://server/folder/archive.tib /ftp_user:usr1  
/ftp_password:pswd1
```

- This will create an image of partition 2-1 in the archive.tib file located on the FTP server.

2. Restore disks and partitions

```
trueimagecmd /deploy /filename:"C:\Test\1.tib" /partition:2-1
```

- This will restore partition 2-1 from image 1.tib.

```
trueimagecmd /deploy /filename:"C:\Test\1.tib"  
/password:qwerty /harddisk:2
```

- This will restore hard disk 2 from image 1.tib, protected with password 'qwerty'.

```
trueimagecmd /deploy /filename:"C:\Test\1.tib" /partition:2-1  
/target_partition:1-1
```

- This will restore partition 2-1, stored in image 1.tib, to partition 1-1.

```
trueimagecmd /deploy /filename:"C:\Test\1.tib" /partition:2-1  
/target_harddisk:3 /start:63 /size:64000 /type:logical
```

- This will restore partition 2-1, stored in image 1.tib, to hard disk 3. A new logical partition will be created on disk 3 from 63 to 64000 sector.

```
trueimagecmd /deploy /filename:z:\Server30Cdrive.tib  
/partition:1-1 /target_partition:2-1 /type:active  
/password:123qwe
```

- This will restore partition 1-1, stored in image Server30Cdrive.tib, protected with password '123qwe', to partition 2-1. The restored partition will be of active type.

```
trueimagecmd /deploy_mbr /harddisk:1 /asz:2 /index:3  
/password:pswd
```

- This will restore MBR from the image of hard disk 1 to the same hard disk 1. The image is contained in the backup 3rd created in the archive number 2, located in Acronis Secure Zone that is protected with the 'pswd' password.

```
trueimagecmd /deploy_mbr /harddisk:1 /target_harddisk:2  
/filename:ftp://server/folder/arc.tib /ftp_user:fuser  
/ftp_password:fpswd
```

- This will restore MBR from the image of hard disk 1 to the hard disk 2. The image is contained in the arc.tib file located on the FTP server.

3. Back up files

```
trueimagecmd /filebackup /filename:E:\Backups\Myproject.tib  
/include:D:\Workarea\MyProject /exclude_names:  
D:\Workarea\MyProject\Old /exclude_hidden
```

- This will back up files from the MyProject folder residing in D:\Workarea, except for files in the Old subfolder and hidden files, to the file Myproject.tib and save this file in E:\Backups folder.

4. Restore files

```
trueimagecmd /filerestore /filename:E:\Backups\Myproject.tib  
/original_date
```

- This will restore all files from E:\Backups\Myproject.tib to the original folder and assign the files the original date and time. Since the /overwrite option is not specified, the latest files modifications will be replaced with the original ones.

5. Consolidate backups

```
trueimagecmd /pit_info /filename:\\smbsrv\Archives\Kons.tib
```

- This will display the numbered list of backups, contained in the archive Kons.tib residing on the network share \\smbsrv\Archives\.

```
C:\Program Files\Acronis\TrueImageEchoServer>>trueimagecmd /pit_info /filename:\\  
srv\elenal\kons.tib  
Pit number: 1  
  type: image; kind: base; date: 6/27/2007 11:39:10 AM  
Pit number: 2  
  type: image; kind: incremental; date: 6/27/2007 11:43:13 AM  
Pit number: 3  
  type: image; kind: incremental; date: 6/27/2007 11:44:04 AM  
Pit number: 4  
  type: image; kind: incremental; date: 6/27/2007 11:48:22 AM  
Pit number: 5  
  type: image; kind: incremental; date: 6/27/2007 11:50:32 AM  
  
Operation has succeeded.
```

```
trueimagecmd /consolidate
/filename:\\smbsrv\Archives\Kons.tib
/target_filename:D:\Kons_new.tib /include pits:2,4,5
```

- This will create on the disk D: an archive consisting of three files Kons_new.tib, (pit 2 of the archive \\smbsrv\Archives\Kons.tib, former \\smbsrv\Archives\Kons2.tib) Kons_new2.tib (pit 4, former \\smbsrv\Archives\Kons4.tib) and Kons_new3.tib (pit 5, former \\smbsrv\Archives\Kons5.tib).

6. Convert an image to virtual disk

```
trueimagecmd /convert /filename:C:\MyBackup.tib
/target_filename:C:\MyHDD.vmdk /vm_type:vmware /harddisk:1,3
```

- This will convert images of disks 1 and 3, contained in the file C:\MyBackup.tib, to the virtual disks C:\MyHDD.vmdk and C:\MyHDD2.vmdk for using with VMware type virtual machines.

7. List

```
trueimagecmd /list
```

- This will list available partitions.


```
trueimagecmd /list /asz
```

- This will list contents of the latest image located in Acronis Secure Zone.

8. Acronis Secure Zone: managing backups by archive numbers

```
trueimagecmd /asz_content
```

- This will list the Acronis Secure Zone size, free space and contents.



```
C:\Program Files\Acronis\TrueImageEchoServer>>trueimagecmd /asz_content
ASZ size: 34439215104 byte
ASZ free space: 34409676800 byte
ARCHIVE number: 1
    index: 1; type: file, base; creation time: 4/2/2007 3:52 PM
ARCHIVE number: 2
    index: 1; type: file, base; creation time: 4/2/2007 4:04 PM
    index: 2; type: file, incremental; creation time: 4/4/2007 6:31 PM
    index: 3; type: file, incremental; creation time: 4/4/2007 6:32 PM
```

In our example, the Acronis Secure Zone contains two archives. The older archive #1 consists of one full (base) file-level backup created on 4/2/2007 at 3:52. The second archive contains a base file-level backup with two increments. You can restore data from any backup as follows:

```
trueimagecmd /filerestore /asz:2 /index:2 /target_folder:e:
```

- This will restore files and folders from the backup created on 4/4/2007 at 6:31 PM with their original paths to the root of partition E.

```
trueimage /list /filename:asz://2 /index:3 /password:aszpw
```

which is equal to:

```
trueimagecmd /list /asz:2 /index:3 /password:aszpw
```

- This will list content of the backup 3rd created in the archive number 2, located in Acronis Secure Zone that is protected with the 'aszpw' password.

9. Acronis Secure Zone: managing backups by file names

```
trueimagecmd /asz_files /password:aszpw
```

- This will list the Acronis Secure Zone size, free space and contents using generated filenames.

```
C:\Program Files\Acronis\TrueImageEchoServer>>trueimagecmd /asz_files /password:aaa
aaa
ASZ size: 5387526144 byte
ASZ free space: 4363010048 byte
FILE name: AAA2.TIB; size: 56414317 byte
type: image, base; creation time: 2/16/2007 3:43:34 PM
type: image, incremental; creation time: 4/25/2007 11:44:47 AM
FILE name: FAAA.TIB; size: 3125550 byte
type: file, base; creation time: 8/22/2006 12:28:40 PM
FILE name: FAAB2.TIB; size: 5147 byte
type: file, base; creation time: 8/14/2007 2:17:45 PM
type: file, incremental; creation time: 8/14/2007 2:19:43 PM
```

In our example, the Acronis Secure Zone contains three archives.

The archive AAA2 (2 stands for number of backups in the archive) consists of:

- full (base) image backup created on 2/16/2007 at 3:43
- incremental backup created on 4/25/2007 at 11:44.

The archive FAAA (F means that this is a file-level archive) contains one base file-level backup.

The archive FAAB2 (B means that this is the second file-level archive in the zone) consists of:

- full (base) file-level backup created on 8/14/2007 at 2:17
- incremental backup created on 8/14/2007 at 2:19.

```
trueimagecmd /filerestore /filename:asz//FAAA
/target_folder:e: /password:aszpw
```

- This will restore files and folders with their original paths from the sole base backup FAAA to the root of partition E.

```
C:\Program Files\Acronis\TrueImageEchoServer>>trueimagecmd /filerestore /filename:asz//FAAA /target_folder:e: /password:aaa
[#####] 100%
Operation has succeeded.
```

10. Acronis Secure Zone: deleting backups

```
trueimagecmd /asz_delete_files /password:aszpw
/filename:FAAB.tib
```

- This will delete the most recent backup in the FAAB archive.

In our example (7), the incremental backup created on 8/14/2007 at 2:19 will be deleted.

The next execution of the same command will delete the base FAAB backup. By continuing with the FAAA and AAA names, you can clear the Acronis Secure Zone except for the last remaining base backup that cannot be deleted.

11. Clone

```
trueimagecmd /clone /harddisk:2 /target_harddisk:3
```

- Clone hard disk 2 to hard disk 3.

12. Explore image

```
trueimagecmd /explore
/filename:\\myserver\backup\mybackup.tib /net_user:john
/net_password:qwerty
```

- This will connect all images, stored in file mybackup.tib on the network drive, as virtual drives.

15.1.5 Ebasrvdb.exe tool: generate an XML file with the backup mapping details

Syntax:

```
EBaSrvDB.exe /filename:<path to the XML file>
```

The purpose of this tool is to provide a way to understand the mapping between a specific backup done on a specific computer at a specific time and the name of the file stored on the backup server. While this information can be useful in case of disaster recovery, it should not be used to manipulate directly the file stored on the backup server. Doing so may lead to inconsistencies in the backup server management and result in turning the archives unusable through backup server or even directly.

The EBaSrvDB.exe tool has to be executed on the same machine where the Backup Server resides. The generated XML file can be located anywhere as long as the EBaSrvDB.exe tool has the write access to it.

If a file with the same name already exists at the target location, it will be overwritten without any warnings.

15.1.6 Adv_report.exe: a report generation tool

Syntax:

```
adv_report.exe c:\<filename>.zip
```

The tool gathers system information and packs it into a zip archive. The collected information will help Acronis Support to provide quick and efficient response.

Specify the file name and the path where the tool will save the generated report. If the name and path are not specified, the AdvReport tool will save the report in C:\Program Files\Common Files\Acronis\AdvReport\adv_report.zip

By default the tool is located in

C:\Program Files\Common Files\Acronis\AdvReport.

Adv_report.exe [arguments]

-help – outputs help information about **Adv_report.exe** commands.

15.1.7 Command-line mode usage under DOS

For use in the MS-DOS-compatible environments Acronis True Image Echo Server includes the **TrueImageCmdDos.exe** which is located in the folder where Acronis True Image Echo Server has been installed, by default it is

C:\Program Files\Acronis\TrueImageEchoServer.

15.2 Scripting

15.2.1 Script execution parameters

Scripts are executed by the **TrueImageTerminal.exe** utility located in the Acronis True Image Echo Server installation folder (i.e. C:\Program Files\Acronis\TrueImageEchoServer). This utility is also used to monitor backup progress.

TrueImageTerminal execution parameters:

TrueImageTerminal.exe [arguments]

Arguments include the following:

/help – outputs help information about TrueImageTerminal.exe parameters.

/progress – outputs progress of backup operations run either from Acronis True Image Echo Server graphics user interface, or from the script.

/execute: [script file name] – executes a script. If there are several scripts to be executed, they are queued. An example for executing MyBackup.tis script:

```
TrueImageTerminal.exe /execute:C:\MyBackup.tis
```

/nowait – an optional script execution argument. Enables to terminate TrueImageTerminal before backup is finished. Example:

```
TrueImageTerminal /execute:C:\MyBackup.tis /nowait
```



By pressing **Ctrl+C** you can force backup progress output off and switch TrueImageTerminal to background operation.



You can terminate backup operation executed by TrueImageTerminal by pressing **Ctrl+B**.

15.2.2 Script structure

Scripts are written in the XML language and you can use the following tags:

Source. Specifies the partitions or disks to be imaged. Letters assigned to partitions must be used without a colon. Disk numbers correspond to their system numbers. To create images of several partitions or disks, use the SOURCE tag for each of them, e.g.:

```
<source letter = "C" />
```

```
<source letter = "D" />
```

```
<source disk = "1" />
```

```
<source disk = "2" />
```

Target. Specifies the name and the location of an image file, e.g.:

```
<target file="E:\Mybackup2.tib" username="username"  
password="password" />
```

username and *password* parameters are optional. They are used to access networked resources.

As a target for the image files you can indicate CD-R/RW or tape drive.

Options. This tag can be used with a number of additional parameters:

Compression: specifies the backup compression level. Can be *None*, *Low*, *Normal*, *High*.

Incremental: specifies whether you need to create an incremental image file. If equal to "false" (or "0"), a complete image file will be created. If there is already a file with the name specified, it will be replaced without warnings. If equal to "true" (or "1") and there is already a file with the name specified, an incremental image will be created. Otherwise the program will create a complete image file. The default value for this parameter is "true".

Description: adds a description to an image file. The comment must be a single string (though its length is not limited.)

Split: splits a large image file into a number of smaller files of the specified size, which can be provided in bytes, kilobytes, megabytes, etc.

Password: adds password protection to an image file.

15.2.3 Script usage examples

The following example illustrates the usage of a script to backup two partitions (logical drives), C and F. *mybackup2.tib* is specified as an incremental image file. High compression level is selected and the image is to be split into 650MB parts for recording to CD-R/RW media. Password protection will also be added. The entire script must be located between the `<backup>` and `</backup>` tags.

```
<? xml version="1.0" encoding="utf-8" ?>
<backup>
<source letter ="c" />
<source letter ="f" />
<target file="e:\mybackup2.tib" />
<options compression="high" incremental="true"
description="this is my backup" split="650 Mb" password="" />
</backup>
```

The script for backing up to tape (tapeN specifies the tapes numbers):

```
<? xml version="1.0" encoding="utf-8" ?>
<backup>
<source letter ="c" />
<source letter ="f" />
<target cdrw="\taperecorder\\.\tape0|||" />
<target cdrw="\taperecorder\\.\tape1|||" />
<options compression="high" incremental="true"
description="this is my backup" />
</backup>
```